9. Scrub nails of each hand with 15 strokes using microbial agent.
10. Holding the brush perpendicular scrub palm, each side of thumb and fingers and posterior side of hand with 10 strokes each.
11. Scrub from wrist to 5cm above each elbow.
12. Entire scrub should last for 5 to 10 minutes.
13. Discard brush to soiled bin.
14. Take care not to touch the tap or sides of the sink during the procedure.
15. Use a sterile towel to dry one hand moving from fingers to elbow.
16. Repeat drying of the other hand using a different towel/use one side to dry one hand reverse side for other hand, if only one towel in available.
17. Discard towel to the solied bin.
18. One assist person to stay while surgical hand washing.

After care:

- Turn off water.
- Towel should be sent to laundry for washing.
- Washed nail brush to be kept in disinfectant solution tray.
- Soap to be kept in soap box and antiseptic solution to kept in cupboard.

WEARING OF GOWN, GLOVE AND MASK

4.3 Gowning

Wear clean or disposable gowns or plastic aprons during procedures to prevent the nurse's uniform likely to become soiled.

Indication:

1. When the nurses changes the dressings of a client with extensive wounds, burns.
2. During delivery procedure and surgical procedure.
3. Client with more susceptible to infection.
4. For strict aseptic diagnostic procedures like FNAC. Lumber puncture, bone marrow biopsy etc.

Purpose:

1. To prevent soiling of clothing during contact with the patient.
2. To protect health care personal from coming in contact with infected materials.

Steps to procedures:-

1. Pick up a sterile gown and allow it to unsoiled keeping inside of the gown towards the body without allowing the outside of the gown to touch any area.
2. With hands at shoulder level, slip both arms into armholes simultaneously. Ask the assisting nurse to bring the gown over shoulder.
3. The assisting nurse fastens the ties at the neck. Overlap the gown at the back as much as possible and faster the waist, ties or belt.
4. Prevent the gown from becoming wet.
5. While removing the gown avoid touching soiled parts on the outside of the gown. Roll up the gown with soiled part inside and discard in the appropriate container.

Practical 4_284-289.indd 287 07/05/18 3:17 PM