
### Type Tool ( )

The Type tool is used to enter and edit text. To create a text frame, select the Type tool and drag the tool in the document window. To select the Type tool, press **T**. When you have the **Selection** or **Direct Select** tool chosen in the Tool panel, you can switch to the Type tool automatically by double-clicking any text frame. InDesign places the text cursor as close as possible to where you double-clicked.




### Path Type Tool ( )

The Path Type tool is used to enter and edit text on a path (Adobe calls this the "Type on a Path" tool). To add text on a path, select the Path Type tool and click the tool on a path. A flashing text insertion point (or text cursor) appears on the path. At this point, text you enter will flow along the path. To select the Path Type tool, press **Shift +T**.

### Note Tool ( )

You use the Note tool to add non-printing notes to text. Click the Note tool in text, and InDesign will display a window you can use to enter the text of the note, or to jump to the next or previous notes in the document.

### Pen Tool ( )

The Pen tool is used to draw paths containing both straight and curved line segments (that is, paths containing both curve and corner points). Press P to select the Pen tool. Click and drag to create a series of connecting points that result in a custom drawn line or shape.

Under the Pen tool, you'll find the Add Anchor Point tool, the Delete Anchor Point tool, and the Convert Direction Point tool.

### Add Anchor Point tool ( )


When you click the Add Anchor Point tool on a selected path, InDesign adds a point at that location on the path.

### Delete Anchor Point tool ( )

When you click the Delete Anchor Point tool on a point on a selected path, InDesign deletes it.

### Convert Direction Point tool ( )

When you click the Convert Direction Point tool on a point on a selected path, InDesign converts the point to the other kind of point—if the point you click is a corner point, InDesign converts it to a curve point; if it's a curve point, InDesign converts it to a corner point. You can also use the Convert Direction Point tool to adjust the direction handles of a point.




### Pencil Tool ( )

The Pencil tool (press N) is used to sketch free form paths. As you drag, it creates a path that follows the cursor, automatically placing points and adjusting control handles as it does so.



XII CompTech_English version CHAPTER 02.indd 54 01-03-2020 13:04:34