

WORD XP

The first thing you have is more options for correcting and formatting text. So let the words flow as your fingers fly over the keyboard in tandem with thoughts and ideas


Formatting with style

While typing long documents it is generally a good idea to stick to a certain type of format for sections within the document. Word XP has a feature for styles and formatting on the task pane. You could use the existing style or add a new style to the task pane formatting list.

If the task pane is not visible, enable it from the View menu. Choose Styles and Formatting from the task pane. This provides you with a rich list of formatting styles. Select the text you want to apply the formatting to and click on the required format. You can add new, customised formatting by clicking the New button. This is a good way to reduce mouse clicks for reformatting text every now and then.

Document-wide format changes

Word XP has options to make document-wide changes to a particular format. Open the task pane and select Styles and Formatting. Select any of the formats you want to change, click on the




Select text with similar formatting

arrow that appears near that format and choose 'Select all _ instance(s)'. This highlights all the text with that format, allows you to make modifications, and gives you the option to choose another format. This makes it easier, especially when you want to make document-wide changes for a particular style, which you

have used in specific sections throughout the document.

Count repetitive words

At times you might want to count the occurrence of a particular word in the document. Word XP allows you to count the occurrences easily. Press [Ctrl] + [F]



Check on words repeated often


to open the Find dialog box and type the word for which the count is required. Enable the 'Highlight all items' check box. Now click 'Find all'. Word XP shows the count for the word you have typed in the Find box and also highlights all the occurrences of that word, so that changes, if any, can be made easily. This is a simple way to find repeated words instantly.

Back up Autocorrect entries

Suffering from OS-related problems? In the worst-case scenario, you might want to reinstall the OS or the application. In such cases, all the entries you have made to your Autocorrect dictionary might be lost. Word XP allows you to back up your Autocorrect entries. Open the file Support.dot from C:\Program Files\Microsoft Office\Office10\Macros. The file displays three buttons. Click the AutoCorrect Backup button. This gives you an option to Backup, Restore or Cancel. Choose the appropriate action to either back up or restore Autocorrect entries.

Change colour code

Tired of those old red underlines pointing out your spelling mistakes again and



Change colour of the error-signifying line

again? Then change the colour! Word XP has an easy registry tweak that can change the colour of the error underlining, besides the grammatical errors signifier. Open the Support.dot file from C:\Program Files\Microsoft Office\Office10\Macros. Click the Registry Options button from the table. From the window that pops open, choose SpellingWavyUnderlineColour and click on Choose Colour. A window pops up from which you can select the colour you want the misspelled words to be underlined with. Click the Change button. The next time you start Word, all words wrongly spelt would be underlined with the colour you have chosen. To change the underlining colour for possible grammatical errors, click GrammarWavyUnderlineColour. To change the underlining colour for possible formatting errors, click FormatConsistencyWavyUnderlineColour.

Working your own way

Word has a default setting of Autocorrect set to correct and capitalise words as and when you type. Word XP allows you to control the way Word changes the words you type. When you place the cursor on the word that has been automatically changed, Word displays a small blue box. (This option is one of

Ad will come