




Customise user settings in CesarFTP

in a split window. The left-hand side of the window shows the status, such as whether the user is connected or not, and other such miscellaneous details. The right-hand side pane lists ping details and the requests made by each user in a text form. All buttons and menus are self-explanatory. Now we'll just whiff the main options which are needed to get your FTP server up and running.

You need to create user accounts before anyone can use your FTP server, or at least an anonymous user account for everyone to log on to the server. CesarFTP allows you to create different groups and share various sets of files with separate groups. Users can be created and assigned to the groups of your choice. You can create a group of close friends, a group of not-so-close friends, and an 'others' group. It's even possible to share only very minimal files with the 'others' group while at the same time sharing everything with your group of 'close friends'.

it 'Close friends', for example, and create another group by name 'XXX' (this can be any name you like). Create users by clicking on the 'Add User' button and assign them to appropriate groups in which you want them to be present. Here you can also set the options for whether the user has to login with a user name and password or can be given anonymous access. Setting up rights and privileges for users accessing your FTP server is wholly at your discretion. Once the users and groups are created you can share files by clicking on the 'File Access Rights' button to add or delete shares.

When you are done with this, you are ready to start your FTP server. Click on the traffic lights icon on the control bar and start the server. You will see a confirmation text on the right-hand side of the window that the FTP server has been started at default port 25 successfully.

Congratulations! All configurations are complete and your server is up and

To do this, observe the traffic light in the main window. If it's green, click on it to shut down the server temporarily. Then click on the button with the icon representing a man in the controls bar below the menu. This brings up the 'User Group & Settings' option. Click on the 'Add Group' button to create a new user group. Let's name

running. Tell your friends to get online immediately and connect to your FTP server. They can use either the console mode or an FTP client or browser. Just tell them to enter **ftp://yourip** and they will be prompted to log in. As soon as your friends give the proper account details that you've set for them, they'll be able to log on. Once logged on, they can access all the files that you want to show them. For example, if a not-so-close friend visits, you can prevent access to certain files.

The main course

If the food of the undernourished soul is music then streaming audio makes for a fulfilling main course. You can turn your computer into a digital music station for broadcasting music.

Setting up the server

The first part of getting your streaming audio server up and running is not difficult. We recommend AnalogX Simple-Server:Shout streaming server because it is



If you have registered a proper domain like **www.domain_name.com**, then you can log on to the site of the domain name provider and set your URL to point to your own static IP provided by the DSL/cable service company.

the simplest and the easiest to configure. Install the application by invoking setup. Once the installation is complete, launch the server. The application opens as a small

Compass to your Computer

For ensuring a 24-hour access to your PC you require a static IP address. While people with a DSL connection might have one, most others will have to use a URL redirection utility, which directs your domain visitors to the new IP every time your machine is assigned one.

STEP 1 Go to **www.dns2go.com** and download the software. Register a friendly domain name that you could share with your friends. For this exercise we used the domain name **tintinsclone.dns2go.com**. Once you have completed the registration process for the domain name, you will be sent a registration key via e-mail. You need to use this registration key to activate your domain using the DNS2GO software.

STEP 2 Install the DNS2GO software on your PC. Start up the software after installation. You are prompted with a registration window in which you enter the domain 'tintinsclone.dns2go.com' and the registration key that you received via e-mail. Clicking OK will send details to the server. As soon as the information has been updated, the software connects your PC to its parent server. The 'Status' tab lets you monitor the status of the current connection.

STEP 3 The 'Service settings' tab is where you set the redirection of the requests made to your domain. Whenever you are online, you can set the software to point to your current IP. This means that visitors to

www.tintinsclone.dns2go.com will be redirected to your local machine for page requests.

All this happens so transparently that the user accessing your Web page won't worry about where he or she is accessing the Web page from.

STEP 4 The software also lets you specify options when you are offline. You can choose to display a default offline page to the user who accesses your page or redirect him/her to another Web site. All this information is stored in your profile on the **dns2go.com** site.

So your software need not be actually working to redirect and route requests.