

drag the paint brush over the text once. Unselect the text by going to **Selections > Select None**. Now go to **Effects > Edge Effects > Dilate**. This will increase the lighter areas of your text.

Go to **Adjust > Blur > Blur more**. Create a watery effect, by going to **Effects > Artistic Effects > Hot wax coating**. This will create a liquid effect. To add some colour, go to **Adjust > Colors > Red/Green/Blue**, and use Red: 0; Green: 20; Blue: 100.

Note that all colours are possible.

■ Burnt edges

Open an image, and select a white background, set to 16 million colours. Use the Magic Wand tool, and click on the white area around the image. Invert the selection by going to **Selections > Invert**. This will allow you to work only on the image, and not the white border. Use the Paint Brush tool with white as your foreground, and create an edge as if has been burnt.

Click **Selections > Select None**, and select the white areas again, using the Magic Wand tool. Invert the selection, and if you wish, feath-



Burnt Edges Effect

er the selection by 2 or 3 pixels. This will give you a smoother edge. Use the Air Brush tool with black as your foreground colour. Select a brush size of 10, and opacity 50. Go around the image close to the edges to create a dark border. Use opacity of 20 to create a lighter border, further in from the darker one. You can also use dark brown to give more realistic burnt edge effect.

■ Flying text

Start with any colour background. Choose a font, and some text. Press **[Ctrl] + [C]**



Flying text effect

to copy the text to clipboard. Now, unselect your text. Flatten the image by clicking **Layers > Merge > Merge All (Flatten)**. Then, go to **Image > Rotate > Rotate Clockwise 90**. Next, go to **Effects > Distortion Effects > Wind**. Set the strength at 100, from the Right.


Then, go to **Image > Rotate > Rotate Anticlockwise 90**, to bring the image back to its original position. Now paste the text you had copied to the Clip Board. Flatten the image once again. Now, click the Selection tool from the tool bar, and drag it across your window effect to cover the effect in the selection rectangle.

Now go to **Effects > Geometric Effects > Perspective-vertical**. Set the Distortion to 100 and Color to the background colour you are using. After that, unselect, and you're done.

■ Creating styled lines

To create a styled line, press the arrow or preview window for Styled Lines on the Tool Options palette, then press the Custom button at the bottom on the Line Style selection list.

Here, you can manipulate several line properties. To set one of the caps, press the arrow button near the caps preview window, to get the selection box. Choose the cap you want by clicking it. You can then set the cap size relative to the line width, by pressing the cap's Size button and then setting the Height and Width for the cap. You add dashes and gaps in the Style pane of the Styled Line dialog box. The first time you press Add, you add a dash, which you can size by setting a value with the Length control, or by dragging the pointed




With Paint Shop Pro 8, you can create your own Styled Lines.

thumb in the control box. Press Add again, to add a gap. You can keep adding dashes and gaps.

To save your styled line, press the 'Save As New' button. Once you save your new line style, it's available with any drawing tool. You can create styled lines for all sorts of purposes, including navigation buttons for a Web site, or separator bars for a Web site, or newsletter.

■ The Seamless Tiling effect

Turn any selection into a seamless pattern for applications such as painting, adding text, or creating



The Seamless Tiling Effect in PSP 8

backgrounds, with the Seamless Tiling Effect under the **Effects > Image Effects** menu. This feature gives you the option to create tiles using three methods. Try this effect. You are sure to like it.