



SECRETS THAT KEEP YOU AHEAD IN THE RACE

TIPS

Adobe Premiere Pro CS3 1
 Adobe Acrobat 9 3
 WavePad 7

30 MINUTES EXPERT

Pictomio 4
 SystemRescueCD 6

ADOBE PREMIERE PRO CS3


Rotoscoping

Rotoscoping is adding effects to a movie frame by frame—basically painting stuff onto a movie. This was the technique used to make the lightsabers in the *Star Wars* films. To rotoscope using premiere, you have to export the file as a filmstrip, and then edit the frames using photoshop or an equivalent software. First select the part of the movie you want to export into filmstrip. The work area bar is just below the timescale in the timeline sequence window. Ideally, select durations less than five seconds, as anything larger than that is liable to crash the image editing software. Go to **File > Export > Movie**, the export movie window will pop up. By default, premier exports the movie as an AVI file. Go to **Settings > General > File Type** and select **FilmStrip** in the drop down box. Then select the **Range as Work Area Bar** instead of **Entire Sequence**, else premiere will crash. You now have a grid of frames you can edit frame by frame. The filmstrip is saved as a .flm file.

Scaling The Video

While handling videos imported from camcorders, digital cameras or mobile phone clips, a common problem is that the videos are too small and there is an empty black space on the screen. This persists as a large black frame around the movie even when the project is rendered.

To solve this problem, select the clip, go to **Effect Controls > Motion > Scale**. The scale slider slides from only 0 to 100. Click on the number 100, and you can enter a numerical value for the scale here. Put in 250, or 200 depending on how much you want to resize the clip.



Enter values to increase the scale beyond 100

Alternatively, you can click once on the video, and resize it using the mouse. To make premiere automatically take care of this problem every time you import a clip, go to **Edit > Preferences > General** and then check **Default scale to frame size**.

Autosave

Most Adobe applications automatically save the file after five minutes. For some reason, in premiere, the default is twenty minutes. To change this, go to **Edit > Preferences > Autosave**. Change the **Automatically save every value** from 20 to 5. Then click OK.

Re-establish Media Links

If you are working on a large project for a long time, and during the course of the work, if you change the names of the

base files or place them in a different folder, then the project in premiere will retain the edits you have made, but lose the link to the file. If there are a lot of cuts or edits, this may seem like the end of the world. Simply right-click on the file in the bin, select **Link Media** then look up the file in the browser and click OK.

Leader

A counting leader is often used at the start of a clip to allow minor adjustments on a projector, check if everything is working normally, and to leave some buffer time before the video starts. To include one in your file, right-click on the bin, select **New Item > Universal Counting Leader**. You can change the wipe, background, line, target and numeral colors according to your choice. Then drag and drop the leader on to the beginning of your timeline.

Panel Full Screen Toggle

It is sometimes necessary to make very minor adjustments in the timeline panel, or adjusting the keyframes in the effects panel. To make these slight adjustments, it is possible to put any panel on fullscreen mode. To do this, select the panel, then press the [`] key (it's just before the [1] key). Press the same key again to get out of the full screen mode.

Watching the program sequence or a monitor on full screen without rendering the project first will however make for a very jerky viewing.

Saving Workspaces

As and when you work with premiere, you will learn to retain the most used panels and toolbars, along with a customized layout. Premiere automatically loads the last used layout every time you start up. If there is a particular layout that you are most at ease with, then save it by going to **Windows > Workspace > New Workspace**. Enter a name for your workspace in the pop up and click OK. Now the workspace name should appear in the **Windows > Workspace** menu itself. Additionally, a shortcut key for the workspace is automatically assigned. If you are doing this for the first time, it should be [Alt] + [Shift] + [5]. This simple measure also prevents other users from messing up your workspace.