



be displayed on the Paintbrush section of the Left Panel. Select the desired image and next when you use that preset, the image will be displayed on the canvas.

Saving

To save the image that you have made or manipulated, either go to File on the menu bar and then click on 'Save As'. This will give you more options and formats to save your image. By pressing **[Ctrl] + [S]** or clicking on 'Save' from File in the menu bar, you get quick JPEG save options. The window that pops up displays JPEG options. There is a preview window on the right and Quality vertical slider on the left. Adjust the quality of the image by moving the slider from Bad to Superb. The quality that is selected will be displayed in the preview window.

If the images are going to be used for web sites, put a check next to Progressive as this will lower the size of the image.

Zoom Player Max 6.0

Although it appears simple, Zoom Player Max 6.0 is a media player that also supports DVD playback. It is packed with loads of features ranging from customising skins and even setting up advanced features like EVR. The Zoom Player has different modes to play different formats such as DVD Mode, Media Mode and even a separate Audio Mode.

Customising Zoom player skins and colour schemes


The first thing you will notice about Zoom Player is its simplistic layout – only the video screen is seen along with the multimedia controls. There is no menu bar of any sort visible by default. Even if you try to press the **[Alt]** key to reveal the menu bar it won't show up. Zoom Player has a different sort of tool bar called the Top Bar.

To reveal this Top Bar, click on the circular icon (Show Top Bar) located on the right side of the multimedia controls. Once that is done, click on the first option – Skin Selector. Alternatively, you can enter the Skin Selector mode by right clicking on the Zoom Player screen and selecting the Skin Selector option from the contextual menu.

The window that is now open is where you can select and configure the theme of the Zoom Player. By default, you can select between two skins – Default and Fusion. More skins can be downloaded from <http://www.inmatrix.com/skins.shtml>. There are many tint presets that will change the basic colour scheme of the player. You can further customise these presets by adjusting the red, green and blue tint with drag controls.

Fixing missing formats

When you initially install Zoom Player, it scans your system for missing add-ons or plug-ins that are needed to support certain file formats. To find out which formats are missing, go to the Options menu by using the shortcut **[Ctrl] + [O]**. Click on the arrow next to System & Files and select Missing Formats. This window will show you two tabs: Important and All. In the Important tab, the formats that are used often and are missing from your system are displayed. Similarly, under the



EVR Advanced options

All tab, all the formats that are missing from the system are displayed. A button will be present at the bottom of this screen that says 'Click here to run the Install Center and install missing components'. Once you click here, you will be asked permission to connect to the internet. Next the Install Center opens where the missing components are checked. This window also gives you information regarding total download size and also the licenses of the missing codecs and addons that you are about to download.

Setting up EVR


EVR is the acronym for Enhanced Video Renderer which basically allows you to play a single video spanning over several monitors. This is a useful feature especially if you have multiple monitors

and want to setup a nice panoramic view to watch movies using Zoom Player. Unfortunately, this feature is limited to Windows Vista and not Windows XP.

Initialise Zoom Player and select Options from the top bar. If it is hidden, you need to click on the small circular icon (Show Top Bar) next to the multimedia controls on the player or use the shortcut – **[Ctrl] + [O]**. Make sure you are in the Advanced mode, or else click on the Switch to Advanced

Mode button. Click on the arrow next to Playback to expand that menu list and then click on Videos and Subtitles. Once here select EVR (Requires Windows Vista or .NET3 installed) option from the drop down menu. Also remember to check 'Allow EVR to span videos across multiple monitors' which falls under the Video Renderer Settings on the same Options screen and then click on Apply and then OK. Now you would also need to get rid of the entire Zoom user interface so that you get only the video playing across your monitors. For this just press **[F7]** and you are set. If you want to restore the user interface press **[F4]**.

For EVR to work properly with Zoom, you will also require to set the Zoom Player to play across all screens. To achieve this, a shortcut needs to be created on the desktop, so right-click on the desktop, go to New and then select Shortcut. Select zplayer.exe from the path which will be located in Program Files under Zoom Player by default. Right-click on the shortcut and select Properties. You will need to add the X, Y, W and H, where X and Y set the top left position of the total video window and W and H are the total Width and Height of the monitors connected. The values will have to follow the Target in such a manner: "C:\Program Files\Zoom Player\zplayer.exe" /X:0 /Y:0 /W: 1920 /H: 1080. **[d]**



Skin options