




The GBridge interface makes sharing easy

to col) is DC++. Free and open source, DC++ is stable and light on resources.

Choosing the client

Some of the popular DC++ clients for Windows are DC++, StrongDC++ and ApexDC++. If you are a very casual user and do not care about the extra features then you can use DC++ otherwise go for StrongDC++ or ApexDC++.

Autoconnect

You can have different nicks and descriptions and even away messages in different hubs if you add them as favourites.

Add a hub to favourites by typing /fav in its mainchat or right-clicking on the hub's tab and clicking on Add To Favorites.

Access the favourite hubs window by clicking on the gold star in the toolbar. You can also use the keyboard shortcut [Ctrl] + [F].

To connect to the hub on start up, make sure the checkbox to the left is checked.

Right-click on the hub name in the list and choose properties to personalise your settings

for that hub. If any field is left blank, the default settings will be used for that field.

Search interval

The default minimum time interval between searches in Apex and Strong DC++ is set to 30 seconds. This gets irritating when you search for many files. This interval can be reduced to 10 seconds.

Navigate to Advanced > 'Experts only' in settings

Change the Minimum search interval from 30 to 10.

In DC++, the default minimum search interval is 0.

Associating file types to folders

ApexDC++ and StrongDC++ can automatically download files to folders based on their extension.

Navigate to Downloads > Favorites in Settings.

Click on add folder and enter the name, path and the file extensions which should be downloaded into this directory.

If you add a favourite folder with extensions AVI, MOV all

the files of these extensions will be downloaded to this directory.

File preview

If you're on a LAN, chances are that a large video will get downloaded in under 10 minutes. However you don't have to wait for the file to finish downloading before you start watching it if you use Apex or Strong DC++.

Navigate to Downloads > File Preview in Settings and click on Add.


Fill in the Name field with the name of the media player you want to use.

For the 'Application' field, browse and choose your

remotely controls your DC client. You can use this to search and download files remotely or monitor uploads. You can even shutdown or log off your system remotely using this web server. You cannot access chat or send PMs using the web UI.

To enable the web server, navigate to Advanced in settings and check the Enable Webserver option.

Go to Experts only in Advanced and set the username, password and port. You can now access the web server by going to the URL http://ip:port/ and logging in using the



You don't have to wait for the video to download completely before viewing it

favourite media player. Don't change the 'Arguments' field.

Finally, type in the extensions for which you want to use this media player to preview.

You can preview a file when it's being downloaded by right-clicking on its download progress bar and going to preview and choosing the media player of your choice.

Enabling web server

Apex and Strong DC++ have an in-built web server that


username and password you set earlier.

If you want to access the webserver over the internet and you don't have a static IP, you can use a service like no-ip (www.no-ip.com) which creates a free hostname to point to your dynamic IP.

The webserver is not available in DC++

Choose the right file listing method

Apex and Strong DC++ have two file listing methods: Get file list and Browse file list. Get file list downloads the entire file list to your computer before opening it, and is the better option if you're on a LAN or have a very fast internet connection. Browse file list downloads only the partial list and downloads more parts as you



DC++ organises your files in to specific folders