


installed the modem yet, it starts up the Add New Hardware wizard to do so. If prompted, insert the Windows XP installation CD, and then click OK. Finally, close all the windows.

In case the PC runs Windows 98, you can install Microsoft Fax from the Windows 98 installation CD. Browse to **Tools\OldWin95\Message\US** and run Wms.exe first and then Awfax.exe. Configure Microsoft Fax by going to **Start > Programs > Accessories > Communications > Fax > Fax console** to bring up the Fax Configuration Wizard. Click Next on the Welcome screen and fill in the Sender's Information such as name, address, etc., in the next screen. This information appears on the fax cover page. Click Next, and choose the modem that you want to use to fax. Here, check the appropriate option to specify whether you want to use that modem only to send or receive faxes, or for both the tasks. If you choose to receive too, you will have the option of manually answering the call or answering it automatically after a certain number or rings. Setting it to receive automatically is useful, especially when you want your PC to receive faxes in your absence.

Click Next and type in the Transmitting Subscriber Identification (TSID) that usually consists of the sender's fax number and name, and appears in the header area of a received fax. In the next screen, type in the Called Subscriber Identification (CSID) that appears on the sender's machine and helps ensure that the fax is sent to the correct recipient. Click Next and you are asked what to do when a fax is received. Choose 'Print it on' if you want the fax to be printed automatically. You can also choose to create a local copy of the fax received by clicking 'Store a copy in a folder' and specifying the fold-




Specify the recipient's information for Microsoft Fax in Send Fax Wizard.

Image Faxing

Windows XP has a Windows Pictures and Fax Viewer that comes in handy when faxing an image or a scanned document. Open Windows Explorer and navigate to the image file. Double-click or right-click the file icon, click **Open With > Choose Program...** and choose Windows Pictures and Fax Viewer from the program list and click OK. When the viewer opens the image, click the printer icon on the toolbar, or press **[Ctrl] + [P]** to print the image. This will bring the Photo Printing Wizard. Click Next to move to the Picture Selection screen. Enable the checkmark for all those images that you want to fax. Click Next and choose Fax as the printer in the Printing Options screen. Click Next to move to Layout Selection screen.

Here you can choose the layout, i.e. the



Use the Photo Printing Wizard to fax scanned documents

number, size and orientation of images on the page. When you click Next on this screen, the Send Fax Wizard will start. Follow the steps of this wizard to send the fax.

er. Click Next, review the settings you chose and click Finish to complete the configuration. You may change the settings anytime by going to **Tools > Configure Fax** in the Fax Console.


Once you complete the Configuration Wizard, the Fax Console opens up. The Incoming folder in the Fax Console contains faxes that are currently being received; the Inbox folder contains faxes that have been received; the Outbox folder contains faxes scheduled to be sent; the Sent Items folder holds faxes that have been sent successfully.

To create a new fax, click 'New Fax' on the toolbar, or go to **File > Send a Fax**. This will start the Send Fax Wizard. Click Next on the Welcome screen and enter the recipient's information such as name, fax number and click Add to add the entry to the recipient list. You can add multiple recipients and also build an address book.

Click Next, choose a template and enter the subject and note for the fax to prepare its cover note. Specify the fax's priority and when you want to send it in the next screen. The final screen shows you the fax summary and also gives you an option to preview it. Click Finish and voila! You have just sent your first fax.

What if you need to fax an MS Word document? Use the Fax printer that is installed along with Microsoft Fax. To fax a file from any application, go to **File > Print**, select the Fax printer in the Print dialog box and click OK. This starts the Send Fax wizard that lets you specify the receiver as discussed above.

Coming to the receiving part, if you have configured it to receive faxes automatically, then you don't need to do anything (remember the Fax Configuration Wizard?). Click the Receive Now button on the toolbar of the Fax Console, if you have configured it to receive the fax manually. Alternatively, activate the Fax Monitor by going to **Tools > Fax Monitor** and click Answer Now.



Schedule when you want to receive fax automatically