

MICROSOFT WORD

Change The Default Open And Save Folders

 When you choose to open a new document in Word, it usually begins browsing in a specific directory, such as My Documents. Similarly, when you choose to save, there is a default directory. You can change these defaults: go to **Tools > Options**. Click on the 'File Locations' tab. Click on 'Documents' under 'File Types', and then on 'Modify'. Use the 'Look in' list to locate the folder you want to use from now on. Click on the folder name, then click 'OK' to select that location. Finally, click 'OK'.

Multiple Clipboards In Word

 You'll often need to copy more than one block of text to the Clipboard, but you probably didn't know you could do this and then paste everything into a document!

To get to the clipboard in the task pane in Word XP, first make the task pane appear using **View > Task Pane**. Then, on the little 'down' arrow, select 'Clipboard'. Click 'Options', then check 'Collect Without Showing Office Clipboard'.

Now copy up to 12 blocks of text (24 blocks in Word XP), then, when you're ready to paste, use the 'Clipboard'

Tips Tricks

SECRETS THAT KEEP YOU AHEAD IN THE RACE

GENERAL TIPS

Microsoft Word	48
Microsoft Excel	49
Microsoft PowerPoint	51
Buying A Laptop	52
Using A Laptop	54

Laptop Security	54
Power-saving Tips	54
Accessories	65

30 MINUTES EXPERT

You've Got A Meeting	50
Stain-free Printing	53

toolbar in Word 2000, or the task pane on the right side of the screen in Word XP. Now, you can paste everything at once, or individual items in different locations. Hover the mouse over the icons on the Clipboard toolbar or on the task pane to get a preview of the content.

Add A Button To A Toolbar

 You've probably never bothered to do this, but it's very easy to add your own buttons to the toolbars. You can add a button for any of a variety of commands. For

example, if you often change the font of selected text to Verdana, you can place a convenient button on the toolbar to make the change with one click. To make a new button, go to **View > Toolbars**. Select 'Customize'. Click on the 'Commands' tab, and select an item under 'Categories'. Then select an item from the list of 'Commands'. Drag the command to a toolbar. A beam that looks like an 'I' will appear to help you install the button. By default, the new button has only a text label. Right-click on the new toolbar item, and select Default Style—the button will become a plain square. Right click on the new toolbar item again. Choose 'Change Button Image', then select a button image. Finally, close the 'Customize' dialog box.

To remove a button from a toolbar, go to **View > Toolbars**, select 'Customize', and drag the button you want to remove off the toolbar.

Print Out All Of Word's Shortcut Keys

 Word has an inbuilt macro that generates a list of all the keyboard shortcuts available. To generate the document, go to

Tools > Macro. Choose 'Macros'. Select 'Word commands' from the list in the 'Macros in' box. Now from the list in the 'Macro name' box, choose 'ListCommands'. Click Run. In the 'List Commands' dialog box, click 'Current menu and keyboard settings'. Click OK. The macro will run, generating a document in table form that you can print.


Using Styles

 A style is a set of formatting characteristics that you can quickly apply to text in your document. The Style list is the pull-down list on the 'Formatting' toolbar, where it usually says 'Normal' in a white box. You can apply styles by selecting text, then choosing a style from the list. There will be a few there by default. To create your own styles, select the text that contains the formatting you want to use for your style. On the Formatting toolbar, click inside the 'Style' box. Type over the existing style name to create the name for the new style, then press Enter. You can set additional formatting characteristics for paragraph styles, such as the style for the next paragraph. To do this, go to **Format > Style**. Click the style that has the settings you want to change. Click 'Modify', and then select the options you want.

Create Your Own AutoText

 AutoText is a way to store and quickly insert text, graphics, fields, tables, bookmarks, and other items that you use frequently. Word comes with a library of AutoText entries. To see there, look at the items listed under AutoText in the 'Insert' menu, or turn on the AutoText toolbar, and then click on 'All Entries'. You can create your own AutoText entries with either of the following methods.

 Choose AutoCorrect or AutoCorrect Options from the Tools menu, then click on the AutoText tab. Type in the text of your new AutoText entry in the 'Enter AutoText entries



In Word XP, you can copy and paste up to 24 blocks of text at once, at different points in your document—using the 'Clipboard' task pane