

Just WAV Doesn't Do It


QUESTION
OF THE
MONTH

Q I bought a new Aiwa CD Player, model XP-V416C, EASS 10 sec, 1-bit DAC, CD-R/RW playback. It can play only Audio CDs. When I convert MP3 files to .wav using mp3 decoder software and burn them onto CD, the player doesn't play anything. But when I copy an audio CD, it plays. I have MP3 Work Shop 2.01 by Donal Riordan. Please tell me how to create an audio CD using an MP3 decoder and Nero Burning Rom 6 Express Edition.

Krishna Caitu

A An audio CD contains audio tracks in RAW form (which is a form of the wave file format), but if you notice, the files on an audio CD are .CDA, just a few KB in size. These files point to the location of the RAW audio tracks on the audio CD, while the tracks themselves are not visible.

You can create an audio CD using Nero Express. To do so, move your mouse over 'Music' in Nero, and click on



Compiling an audio CD using Nero Express

a burning speed of 8x for backward compatibility with older CD players, and click 'Burn'. The audio CD thus created will be playable on any audio CD player.

'Audio CD'. Click 'Add' in the next window, browse to the folder where you have stored your songs, select the songs to be added to your audio CD compilation, and then click 'Add'.

After you are done, click on 'Finished'. Now click 'Next', select

A To enable DMA, Go To My Computer > Properties > Device Manager, and click the 'Hardware' tab. There, expand 'IDE ATA/ATAPI Controllers'. You will find your hard disk and CD-ROM controllers listed under 'Primary IDE channel' and 'Secondary IDE Channel'. Double click 'Primary IDE Channel' and click the 'Advanced Settings' tab. Set the transfer modes to 'DMA if available' for both the Master and the Slave devices—these could be listed as 'Device 0' and 'Device 1'. Repeat the above steps for the Secondary IDE Channel. Once you change the settings, reboot and you are good to go!

DirectX Woes Yet Again

Q I recently installed Windows XP with SP2. I had DirectX 9.0b, but after installing XP with SP2, I am unable to install DirectX 9.0c. I even tried the redistributable version, which was given with the March issue of *Digit*.

Using the Everest diagnostic software, the OS shows up as Windows XP Professional (5.1, build 2600) Service Pack 2, v.2096 (2600.xpsp_sp2_rc1.040311-2315), while the DirectX version is DirectX 9.0b (4.09.0000.0903).

Karan Pratap Singh

A It's evident that you have Release Candidate 1 of Windows XP SP2 installed. Install the final version of SP2, which was supplied with the *Digit* September 2004 DVD. Alternatively, you could download it from the Microsoft Web site.

Where's The Colour?

Q I have an Athlon XP 1700 processor on a Gigabyte KT400 board, 512 MB of SDRAM, and an nVidia GeForce FX 5200 AGP card with 128 MB of RAM. The display card has a 4-pin S-Video out socket. I have a Sony combo drive, and also an LG 52X CD-Writer. I tried connecting my TV using an S-Video to RCA cable (S-Video out to the video-in of the TV). I adjusted the necessary configurations in

'Display Properties', and selected my TV as the secondary analogue clone display.

My problem is that the display on the TV monitor is Black and White. I tried to configure the TV display properties to the lowest resolution of 800 x 600, but am still unable to get the TV to display colour.

K Ramanathan

A Your problem is that your display card's TV output is conformant with a TV standard other than the one for which your TV is configured. There are three widely-used TV standards, PAL, NTSC and SECAM—PAL is the one used in India.

There are three solutions to your problem. The first and best is to install the latest version of the nVidia ForceWare drivers from the *Digit* CD/DVD. Your display card should now correctly detect your TV. Otherwise, you can download and install a utility called TV Tool from <http://snipurl.com/dzfa>. Using this, you will be able to change the TV standard of the TV-out signal of your display card. The third solution is that if your TV supports multiple standards, try changing the TV signal standard of your TV from PAL to NTSC.

Umm, I Deleted Some Folders...

Q I deleted the folders of some unwanted programs, and cannot remove them from the 'Add/Remove Programs' list. How do I do this?

Abhishek Kumar

A To remove entries from the 'Add/Remove Programs' list, use the registry editor. Be very careful when using it: one false move can render your PC unbootable. Click Start > Run, type in 'regedit.exe' and click OK. Go to HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\CurrentVersion\Uninstall. Here you will find the various registry entries that correspond to the entries in the Add/Remove Programs list. Just delete the entries you don't want. ■



Get Help Now!

E-mail us your computing problems along with your contact details to sos@jasubhai.com, and we may answer them here! Since we get more mails per day than we can handle, it may take some time for your query to be answered. Rest assured, we are listening!