

set, a vertical line is inserted. This feature is used in legal documents.

 **First Line Indent**—You can use this selection to set the indent for the first line of a paragraph. Instead of using the **Format > Paragraph** dialog box, position (click) this selection on the ruler bar where you want the indent to be.

 **Hanging Indent**—You can use this selection to set the indent for second and subsequent lines of a paragraph. Instead of using the **Paragraph** dialog box, position (click) this selection on the ruler bar where you want the hanging indent to be.

Setting Tab Stops

 By default, left-aligned tab stops are set every half-inch across the page. To set your own tab stops, you can use the **Tab** selection on the **Format** menu; or you can make tab setting changes directly on the **Ruler Bar**. The tab stops you set yourself will be displayed on the **Ruler Bar** using a separate symbol for each type of tab setting; default tab stops are not displayed.

To set tab stops directly on the **Ruler Bar**, do the following:

Position the insertion point—or select a section of text—where you want the change in tab stops to occur: to change the tab stops for a single paragraph, click somewhere within a paragraph to be changed. To change the tab stops for several existing paragraphs, select (highlight) the paragraphs. This could be the entire document. To change the tab stops for a new paragraph, click at the beginning of a new, blank line (this could be at the beginning of a new document). The new line spacing will continue to each new paragraph when you tap the **[Enter]** key.

If the type of tab you want to use is not already selected, click the tab button at the left end of the **Ruler Bar** and make a selection. Descriptions of tab stop

selection buttons are provided in the next tip.

On the **Ruler Bar**, click at the point where you want to place a tab stop.

Keep clicking until you have positioned all desired tabs.

Using the Tabs Dialog Box

 You can also select the tab alignments and position tabs using the **Tab** option on the **Format** Menu or in the **Paragraph** dialog box. Using this method also allows you to include a leader (such as a dot leader) to a tab stop.


Make desired changes in the **Tab** dialog box, clicking the 'Set' button to set each tab stop. If you want to delete a tab, click that tab setting in the tab listing and then click the 'Clear' button. To clear all tab stops, click the 'Clear All' button. When finished, click 'OK'.

Add a Watermark

 Watermarks add an overall graphic dimension to a newsletter, flyer or letter on a special topic. The watermark is printed in the centre of the page; you can select the size you want. Change its colour in a paint program before you insert it as a background picture. Open a new document, and from the toolbar, select **Format > Background > Printed Watermark**. You will have an option to place either a **Picture Watermark** or a **Text Watermark**.

For a **Text Watermark**, type in the text, its font, size and colour. Explore the 'Layout' and 'Transparency' options. Click 'Apply' and then 'OK'.

For a **Picture Watermark**,




When you choose to insert a watermark, you're given three options. Explore these

you will be able to first select any picture you have available, and then select its size and whether it will appear "washed out" or have more colour. Click **Apply** and then **OK**.

Creating Forms

 You can use the **Forms** toolbar to create documents for onscreen tests, activities, reports and multiple choice quizzes. Forms allow a user to tab through the fields and make changes/additions. Select **View > Toolbars** and check the **Forms** toolbar to select it. This will bring up the **Forms** toolbar. You'll see several buttons:

- 1. Text Form field:** To add text within the document, for fill-in-the-blank forms. The surrounding text will adjust to the length of the answer.
- 2. Check box form field:**



Above: A document with a "washed-out" watermark.

Below: A document with a watermark that has not been washed out. In most cases, you'll want the former

Users can tab through and press **[Enter]** to insert a checkmark.

3. Drop-Down form field: To specify choices for the user to select. The person using the form will need to use the **[Down Arrow]** and **[Enter]** keys to review and make the selection.

4. Form Field Options: Click here to create the choices. Your first choice will show in the box. (You will have to lock the form first in order to see your choice in a pull-down menu.)

5. The two table tools help you to easily create a table to tab through. This is especially handy when creating reports and other classroom forms.

When your information

and fields are entered, use **6. Form Field Shading:** When this is selected, it shades text fields so that the user can see them. The shading does not print out.

7. Protect Form: When you have finished setting up your form, click this button to lock the form. It will prevent the user from changing your form/template. If you want to make additional changes, you will need to unlock the form.

Consider doing the following:

- 1. Highlight the answer field**