

Want to hide some personal files? How would you hide one or more drives of your computer from appearing in your Windows Explorer?

Write in with the subject 'Take a crack', and your postal address, to takeacrack@thinkdigit.com with your solution

How would you hide one or more drives of your computer from appearing in your Windows Explorer?

LAST MONTH'S CHALLENGE

Win!



Take a Crack and win
Ice Age Movie VCD

LAST MONTH'S WINNER

Debangshu Sen
P.O. Burnpur,
Dist. Burdwan
West Bengal

Rules and Regulations

Readers are requested to send in their answers by the 15th of the month of publication.

Employees of Jasubhai Digital Media and their relatives are not permitted to participate in this contest.


Readers are encouraged to send their replies by e-mail. Jasubhai Digital Media will not entertain any unsolicited communication.

Jasubhai Digital Media is not responsible for any damage to your system that may be caused while you are trying to solve the problem.

Ripping Audio CDs in Windows Media Player version 9 and 10 is a piece of cake! Can do you do it in WMP8?

Rip Audio CDs To MP3 In Windows Media Player 8


1. Open the Registry Editor (Start > Run, type "regedit" and press [Enter])



You can set the various MP3 encoding bitrates in the registry

2. Go to the key
HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\MediaPlayer\Settings\MP3Encoding

Here, you'll see sub-keys for LowRate and LowRateSample, which of course equates to the single 56 Kbps sample rate



MP3 Encoding in Windows Media Player 8

you see in Windows Media Player 8.

To get better sampling rates, you have to create the following DWORD values (right-click on the free space on the right pane and select "New". Select "DWORD Value" from the menu that pops up):

"LowRate" with a DWORD value of "0000dac0"

"MediumRate" with a DWORD value of "0000fa00"

"MediumHighRate" with a DWORD value of "0001f400"

"HighRate" with a DWORD value of "0002ee00"

This corresponds to 56, 64, 128 and 192 Kbps.

You may need to restart your PC.

You can change this to your liking using the following DWORD Hex values :

320 Kbps = dword:0004E200

256 Kbps = dword:0003E800

224 Kbps = dword:00036b00

192 Kbps = dword:0002EE00

160 Kbps = dword:00027100

128 Kbps = dword:0001F400

112 Kbps = dword:0001B580

64 Kbps = dword:0000FA00

56 Kbps = dword:0000DAC0

3. Now, when you launch Windows Media Player 8 and go to Tools > Options > Copy Music, and you will see four encoding choices for MP3: 56 Kbps, 64 Kbps, 128 Kbps, and 192 Kbps.

Note: You will not get a higher bit rate encoding unless you have installed an MP3 codec separately on your machine. ☑