

might be tricky to understand. However, if you know about some of the most commonly used options, this might give you a headstart.

- **Auto and No auto** - The auto option helps in mounting the device automatically. It is a default option. If you do not wish to mount the device automatically, select the no auto option in /etc/fstab.
- **User and no user** - These two options are helpful. The user option enables the user to mount the device. The no user option only allows the root to mount on the device. Here the no user option is the default option. If you are unable to mount any CD or floppy, then install the user option.
- **Exec and no exec** - The exec option helps you execute the binaries present on the partition. The no exec option does not lead to accomplishing the binaries present in it, however, it is suitable for when you want to execute binaries in your system. Exec is the default option.
- **Ro** - Read-only or ro is used to mount the file system to read-only.
- **Rw** - Read-write or rw is used to mount the file system or read-write. By enabling rw, it makes it easier to write to your floppies or Windows partitions.
- **Defaults** - To use the default options of auto, ro, rw, sync, exec.
- **dev/nodev** - This option helps to interpret a character in the system. It also helps in blocking special devices in the file system.
- **suid/nosuid** - The suid option helps to permit the operation of sgid bits. Nosuid blocks the process of sgid bits.
- **_netdev** - It is a network partition that mounts after starting the network. It only works with fstype NFS.

```

technit@technit:~$ sudo mkdir /mnt/technit
technit@technit:~$ 
technit@technit:~$ sudo sshfs -o allow_other technit@192.168.0.102:/home/technit /mnt/tec
technit@192.168.0.102:~$ password:
technit@technit:~$ 
technit@technit:~$ cd /mnt/technit/
technit@technit:/mnt/technit$ ls
technit@technit:/mnt/technit$ ls
Desktop  IDS                      Original Virtual Machines  Ravi Songs  Existing
Documents Music              Pictures                   Technet.com  Text
Downloads Old Classy Songs - Ravi Fav Public  Templates  Videos

technit@technit:/mnt/technit$ df -h
Filesystem      Type      Size  Used Avail Use% Mounted on
udev            devtmpfs  738M   0  738M   0% /dev
tmpfs           tmpfs     568M   0  568M   0% /run
/dev/sda1       ext4      31G   5.5G  24G  19% /
tmpfs           tmpfs     740M  218K  740M   1% /dev/shm
tmpfs           tmpfs     5.0M  4.0K  5.0M   1% /run/lock
tmpfs           tmpfs     740M   0  740M   0% /sys/fs/cgroup
tmpfs           tmpfs     130M  24K  130M   1% /run/user/1000
technit@192.168.0.102:/home/technit$ fuse.sshfs 324G  55G  253G  18% /mnt/technit
technit@technit:/mnt/technit$
  
```

Mount Remote Filesystem

Remote Filesystem Listing

Remote Mounted Filesystem

Copyright attribute: <https://www.technit.com/sshfs-mount-remote-linux-file-system-directory-using-ssh/>

Different mount options