


it should open in windowed mode. Set the Registry value back to 1 to revert to your original settings.



You can disable media scanning to improve performance

 Improve Performance

 If you notice your computer becoming sluggish when using Nero Home, you can turn off media scanning. Media scanning scans particular folders for any additional media files (audio/video/etc.) and indexes them for faster searching within Nero Home. To turn off media scanning, open up Nero Home and double-click on the spanner icon, which takes you to the Settings. Next, click on General, and click on Media Scanning Options. Here you can disable scanning for certain file types, select only specific folders you want Nero Home to scan, or disable media scanning altogether.

NERO SHOWTIME

Nero includes Nero Showtime, a full-fledged video player. You can use this to play any audio or video files, and it comes loaded with enough features to rival most video players out there.

Capture Your Videos

 The capture feature within Nero Showtime offers a lot of options to capture frames for your video. You can find this option by right-clicking on Nero Showtime player and clicking on Preferences. Here, click on Capture Frame, and you will be faced with a multitude of options including capturing your images to clipboard where you can paste your images in your favourite image editing software, capturing the frame and setting the image as a wallpaper upon the touch of a button, or printing the captured image to your default printer.

If you choose to capture the image to a file, you can set the location where you want to save the image. The prefix


for the resultant file, unfortunately, cannot be changed.

Customising Skins Manually

Again, you can customise specific areas of your skins however you want and whatever size you want. Go to `C:\Program Files\Nero\Nero 7\Nero Showtime\Skins`. Here pick a skin, for example, red plastic. Copy all three files containing the “red plastic” prefix in their filename and rename the newly-created files to anything similar, for example, Nero.skn, Nero.bmp, and Nero_anime.bmp. Now double click on Nero.skn and you can change the buttons’ size and position. So if you have a problem aiming for that tiny control, or wish it could be replaced with something else, just change those numbers. A tip for changing positions: it’s wise if you choose to replace a button which is almost the same size as one of the others, after which you can switch their position numbers in the .skn file.

Clear Out History Of The Last Played File

In case you weren't aware, Nero Showtime, when started, by default loads the last-played media file. And if



You can direct `defmediafile` to point to any file you want

you click on Play, the last media file will automatically play. Now if you have a file which you, umm, don't want others to know exist on the system, you can clear out its trace from the history. This requires Registry tweaking. Enter the Registry Editor, and navigate your way through to

HKEY_CURRENT_USER\Software\Ahead\Nero Showtime\Settings

Here look for the String value called "defmediafile". Double-click on it and delete its contents to clear out the history of Nero Showtime. A word of

caution—do not keep Nero Showtime open in the background when editing this entry, because after you close the Registry Editor, the entry will still remain in the history of Nero Showtime, as the program saves its settings upon being closed. Also do not forget HKEY_LOCAL_MACHINE—the same change needs to be made there too!

Profile Icons For Your Settings

If you keep changing settings as you view different movies, and don't want to go through the settings every time, you can have icons containing different settings. Sounds neat? But it comes at a price—heavy Registry tweaking. Go back to the key

HKEY_CURRENT_USER\Software\Ahead\Nero Showtime\Settings

There's a large number of settings including brightness etc., functions like radio buttons will have a value of 0, 1, 2, or 3 etc. For example, the "capture to" setting has three radio buttons; setting the value to 0 will set the first radio button, a value of 1 will choose the second option, and so on.

Once you're done editing your settings, right-click on the Settings key in the left-hand pane and click Export. Give it any filename you want; a tip is to include the name of the video file which these settings are for—it's similar to naming presets. Similarly, change the Registry values for your other settings and export them. Now, by just double-clicking the files you created, you can have different settings presets before opening movies.

Balloon ToolTips

 Sick of the drab windows tooltips that come up in Nero Showtime? You can change the look to much more appealing balloon tips. In Options, click on the “tooltips” setting, and click on the “balloon tips” radio button. Now you can hover your cursor over buttons just to see how cool the new balloon tooltips can look compared to the ones Windows has to offer!

COMMONLY USED KEYBOARD SHORTCUTS

Play: [Enter]
Stop: [S]
Pause: [Spacebar]
Previous: [P]
Next: [N]
Step forward: [T]
Seek to time: [Ctrl] + [G]
Options: [Ctrl] + [C]
Full screen: [Z]
Change subtitles: [U]
Menu: [I]
Capture frame: [C]
Eject disc: [J]