

Connection in the side menu. The upload and download speed options are visible in the Transfer menu.

Enabling Transport Encryption

We've talked of transport encryption earlier. Azureus, too, gives you the option of encrypting data. In Advanced mode, select Tools > Options. You will find Transport Encryption under Connection. Check the box "Require encrypted transport". Also check the boxes to enable non-encrypted incoming and outgoing connections.


Disabling Plugins

Azureus may use plugins to add new features to the program, but these plugins also burden the system. You can disable most of the plugins you don't use.

Click on Advanced to the right end of the toolbar. Select Tools > Options. Click on Plugins and uncheck the plugins you don't use. Note that some of the plugins may be shared with other plugins or Azureus itself, so avoid disabling those. (In the Type column, you can see if a plugin is shared.) Click Save and restart Azureus.

Enabling The Torrent Tracker's Web Interface

Azureus has an inbuilt torrent tracker. In Advanced mode, go to Tools > Options, and under Plugins, click "Tracker Web". Make sure the Public torrent details to <tracker_url> box is checked. You can now view information on the torrents uploaded to your tracker. You can alter other settings like setting separate ports for the Web page, and CSS themes for the Web interface. You can find settings for the tracker itself under Tracker > Server.



Enabling the Web interface for Azureus' tracker

Create Torrents In Azureus

Now that the tracker itself is running, you can also create new torrents to share with others over the Internet. Go to File > New Torrent. Click on the "Use an external tracker" radio button and enter the URL for the tracker. Choose whether you want to upload a single file or a folder. Click Next. Here you can enter multiple trackers. Click Next, and choose the path of the file or folder of which a torrent is

to be created. Click Next, and enter the path where you want the torrent file to be created. Choose from the appropriate checkboxes for whether you want to open the torrent for seeding once the torrent is created and if you want to use the inbuilt tracker to host the torrent.

Accessing Azureus Through A Browser


Some plugins allow Azureus to be accessed through a browser. This is particularly useful when you're away from home and want to check on download status and add or change downloads. Swing UI is a plugin for Azureus that lets you do that. Download it from http://azureus.sourceforge.net/plugin_list.php. Download the ZIP file, and unzip its contents into the Azureus\plugins folder. Next, in Advanced mode, go to Tools > Options. Then select Plugins > Swing UI. Here, select the port for the interface and the protocol to be used. We use port 5555 and the HTTP protocol. You can also set a username and password to make access limited to yourself. Click Save and restart Azureus. Now use a browser (preferably Firefox) and load the URL <http://YOURIP:PORT>. (You can find your Internet IP by visiting a site like www.whatismyip.com. Those with ISPs that use PPPoE (PPP over Ethernet) can find their IP address by double-clicking on the Internet dialup adapter's network icon in the system tray. Using services like DynDNS (<http://tinyurl.com/bte78>) is also a good idea if you don't want to keep remembering your IP.) If you set a username and password, you will be asked to enter it. You can now monitor and control your downloads.

Using RSS For Starting Downloads

A useful feature that can help automate downloads are RSS Feed downloaders. These plugins download regular updates from your favourite sites and then pick up torrent files from them and automatically download the files depending on how you set the filters. One of the plugins you can use is RSSFeed Scanner. Find it at http://azureus.sourceforge.net/plugin_list.php.

Download and unzip the file into the Azureus\plugins folder. Start Azureus, and you can configure the feed downloader by going to Plugins > RSSFeed Scanner. First add feeds to the list by clicking the "+" icon in the Feed URL panel. Enter the URL for the RSS feeds and the location where you want the torrents to be saved. You can also choose to add filters so Azureus will only download files of the specified criteria. ☐

LINUX




On this month's DVD, we've given you Fedora 7. We'll be using Fedora to demonstrate the tips that follow, but we're pretty sure you can do the same with other distributions.

Note: Some of the tips we are about to show you might require you to be logged into root.

Adding Windows Fonts To Linux

Many of us are used to Windows so much that the sight of Linux's fonts is unbearable. It is possible to install Windows fonts on Linux. Go to System > Preferences > Look and Feel > Font. Click on the Details button and then on the Go to font folder



Copying Windows fonts into Linux's fonts folder

button. In the window that appears, copy and paste the Windows fonts. Restart or re-login to be able to use the fonts.

Advanced Command Line Traceroute

Those who wish to find the route to a remote server are used to the traceroute command. There is an advanced version of traceroute called mtr available on Fedora and some other distributions. mtr not only shows the route, but refreshes pings to all the nodes up to the destination machine, and also lets you choose from different ways of showing statistics. To use mtr on Fedora, go to