

ernet connection of your choice and once again go to the 'IPv4 Settings' tab on the editing window. You simply have to set the 'Method' to Manual. This should activate the Addresses section on the window. Click on the 'Add' button to create a new line on the list. Enter your IP address under the Address column, the netmask and Gateway addresses and then enter your DNS information in the lower part as we told you earlier. This should get you going.

Connecting to a broadband connection: Not everyone happens to have a wireless router at home but most broadband users would be using the 'dialling' method to get online. Just a few years ago the Linux discussion forums over the internet were filled with questions about how to use the PPPoE (it stands for PPP over Ethernet) or DSL connection on Linux. The Gnome team took the problem seriously and we have in Ubuntu the real easy way to connect to a DSL connection. In case you are wondering whether you already use a DSL connection, we would help you decide. If your answer would be 'Yes' to someone who asked "Do you have a Wired broadband connection and your ISP has given you a Box with a few LEDs blinking but to does not have wireless connection feature and you have to dial from your computer to get connected?", then we believe you are using a DSL connection and this piece of text would suit you.

Ubuntu does not detect that you are a DSL user who dials over the Ethernet wire to get connected to internet. You will have to tell it the fact that you are one. Just click on the networking icon again, and select 'Edit Connections'. On the 'Network Connections' window, switch to the 'DSL' tab and click on the 'Add' button. A new window would come up. This window will have the 'Connection name' at the top of it. By default the name is set to be something like 'DSL Connection 1'. You might set it to something more friendly, such as 'BSNL Dataone Broadband'. On the window, enter your username and password on the DSL tab (should be active by default). That should be it! Simple, isn't it? Well, if you further want to control the IP settings, you can use the 'IPv4 Settings' tab. In case your ISP has allocated a static IP address for you, you can use the 'Manual' method or if you want to simply use DNS servers other than your ISP, you the 'Automatic (PPPoE) Addresses only' method and set the DNS server. Then hit 'Save' and you would be asked to enter the password. Do so and you are ready to dial. Just click on the networking icon again and select the name you entered when setting up the connection. In our case, that would be 'BSNL Dataone Broadband'.