

CSS3 2D transforms

CSS3 2D Transforms module, which enables elements that are rendered by CSS to be transformed in two-dimensional space. 2D transforms are currently supported using the following Transforms properties:

- ▶ The `-ms-transform` property applies a two-dimensional transformation function to an element. It contains a list of one or more transformation functions. Internet Explorer 9 supports all the transformation function specified in the CSS3 2D Transforms module Working Draft (dated-December 1, 2009).
- ▶ The following transformation functions are used with the `-ms-transform` property:
- ▶ The `matrix(a,b,c,d,e,f)` function specifies a 2D transformation in the form of a transformation matrix of six values (a through f).
- ▶ The `translate(tx,[ty])` function specifies a 2D translation by the vector [tx,ty], where tx is the first translation-value parameter and ty is the optional second translation-value parameter. If ty is not specified, its value is zero. (Translation-value parameters can be either percentages or lengths.)
- ▶ The `translateX(tx)` function specifies a translation by the given amount in the x direction.
- ▶ The `translateY(ty)` function specifies a translation by the given amount in the y direction.
- ▶ The `scale(sx,[sy])` function specifies a 2D scale operation by the [sx,sy] scaling vector that is described by the two parameters. If the second parameter is not provided, it takes a value equal to the first.
- ▶ The `scaleX(sx)` function specifies a scale operation by using the [sx,1] scaling vector, where sx is given as the parameter.
- ▶ The `scaleY(sy)` function specifies a scale operation by using the [1,sy] scaling vector, where sy is given as the parameter.
- ▶ The `rotate(angle)` function specifies a 2D rotation by the angle specified in the parameter about the origin of the element, as defined by the transform-origin property.
- ▶ The `skewX(ax)` function specifies a skew transformation along the x-axis by the given angle.
- ▶ The `skewY(ay)` function specifies a skew transformation along the y-axis by the given angle.
- ▶ The `skew(ax,[ay])` function specifies a skew transformation along the x- and y-axes. The first angle parameter specifies the skew on the x-axis. The second angle parameter specifies the skew on the y-axis. If