


Scroll down and check **Turn off all unnecessary animations (when possible)**. Click Apply and then OK to save changes and exit the menu.



DEFRAGMENT THE DRIVES

On Windows 10, your disks get fragmented over time and this, in turn, increases the time it takes for Windows to fetch data. Excessive fragmentation could also lead to disk failure. When you defragment drives, the fragments are combined to create sequential data on the disk that ultimately speeds up operations.



Doing this on a regular basis will improve performance and extend the life of your system as well. Go to File Explorer and select the Local Disk (C:). Now, right-click and then open **Properties**. Click on the **Tools** tab. Under **Optimize and defragment drive**, click on **Optimize**. Now, select the drive you want to optimise and then click on the **Optimize** button yet again.



LEVERAGE THE TRACKPAD GESTURES

Taking a page out of Apple's book, Windows 10 hosts multiple Mac-like trackpad features that can really enhance user experience. The common ones include using two fingers to scroll, pinching to zoom and tapping two fingers on the trackpad to right click. However, there are a few lesser-known trackpad gestures as well, such as the following -

- **Show Open Windows** - To see

all open windows, place three fingers on the trackpad and swipe outwards (away from you).

- **Show Desktop** - To go to the desktop instantly, place three fingers on the trackpad and slide them inwards (towards you).
- **Switch between open Windows** - To switch between multiple open windows, simply place three fingers on the trackpad and swipe right or left
- **Open Cortana** - Tap three fingers on the touchpad
- **Open action center** - Tap four fingers on the touchpad
- **Switch between virtual desktops** - Place four fingers on the trackpad and swipe right or left



SNAP WINDOWS INTO FOUR CORNERS

Windows users have been able to snap applications to the left or right side of their screens since the days of Windows 7, however, with Windows 10, the ability to snap programs doubled. Many still don't know about this feature, and resort to using **Windows + Right or Left** arrow key to have two windows sit side by side. However, if you want four windows in four different corners, you need to simply drag each window to the corner of the screen you want them to be in, and then release once you see an outline of a window taking up a quarter of the screen. To accomplish the same with keyboard shortcuts, simply snap the

window to half first using **Windows + Right/Left**, that you're already familiar with. Then, repeat this step, and then finally press **Windows + Up/Down**.



IMPROVE WALLPAPER QUALITY

Windows usually resorts to lowering the quality of the image used as the wallpaper to 85 percent of the original's quality to save disk space. However, if you want the maximum resolution to be shown, you can change this setting by editing the registry. Press **Windows + R** and type regedit in the Run program. Press OK and allow it to make changes. Now, go to **HKEY_CURRENT_USER > Control Panel > Desktop**. In the right-hand-side pane, right-click and click on New and then click on **DWORD (32-bit) Value**. You've essentially created a new 32-bit DWORD parameter. Rename it **JPEGImportQuality**. Set the value data to 100 and then click OK. Finally, restart your PC.



REPAIR MISSING OR CORRUPTED SYSTEM FILES

If some Windows functions have ceased to work on your PC or if Windows is constantly crashing, you can use the System File Checker to restore missing or corrupted files. First, run Command Prompt as administrator. To do this, type in cmd in Windows search and then right-click on Command Prompt, and click Run as administrator. On Windows 10, you will

