




Set up ADB on your Windows PC

box will pop up, click Allow. Tap on Wireless Debugging and click on 'Pair device with pairing code'. Take note of the pairing code, IP address, and port number displayed. In the command prompt, run the following command-

```
adb pair ipaddr:port
```

Replace ipaddr:port with your IP address:port number that will show up in the pop-up. Next, you will be prompted to enter the pairing code. Enter the one shown in the pop-up under Wi-Fi pairing mode and you will get a message saying you have "Successfully paired to xxx". If you're using Android 10 or lower, head over to this link <http://dgit.in/adbwireless> and follow the tutorial.



BACKUP YOUR PHONE AND RESTORE BACKUP

Those who tinker around with their Android devices will know that Recovery Mode allows users to reset the phone and create backups. However, these backups are stored on the phone storage or SD card. If you want to create a full backup of your phone on your PC, you can do that with some ADB magic. To backup your phone, enter this command-

```
adb backup -all -f
```

```
/backup/location/  
file.ab
```

This command will then back up all your apps and files in a file location specified by you. After entering this command, hit enter and unlock your phone. Give permission to allow the backup of your phone's data. Additionally, you can only set up a password to encrypt your data. Now, to restore the backup of your phone, you can enter the following command-

```
adb restore <backup-  
file-location>
```

Specify where you would like the data to be restored. Also, enter the password you set up to encrypt the data to restore the backup.



CHANGE THE DPI OF YOUR SCREEN

If you want more control over your phone's DPI settings, you can use ADB to achieve this. The DPI value can be changed to get a larger, zoomed-in or a smaller display, as per your needs. Type this command to tweak the DPI of your phone-

```
adb shell wm density  
xx
```

Simply replace 'xx' in this command with any DPI value and the change will be live on your device without having to reboot it. To switch back

to the original DPI, enter the same command with your original DPI value. Be sure to check the original DPI by entering this command before you change the number, so that you can change it back to what it was-

```
adb shell wm density
```



UNINSTALL BLOATWARE

Android smartphones usually come with a fair amount of bloatware, some UIs more than others. These aren't just limited to apps, there are several services running in the background that you can disable by using ADB commands. In order to do this, first the package name of the app or service you wish to remove. You can do this by downloading App Inspector or Package Name Viewer 2.0 from the Play Store for free. These apps will provide you with the package names of apps on your phone, note down the ones you want to uninstall.

Now, head over to your PC and type `adb shell` in your terminal and hit enter. Type the following command to uninstall any app of your choice-

```
pm uninstall -k  
--user 0 name of  
package
```

Insert the package name of the app in place of "name of package" in this command. The app will instantly be uninstalled from your smartphone.



RECORD SCREEN

Most UIs have a screen recording option now, but you can do this via ADB too. The benefit of doing it via ADB is that you won't see any pop-up bubbles or overheads when the screen is being recorded. Type the following command and specify the

path where you want it to be saved in the command-

```
adb shell screenre-  
cord <folder-path/  
filename.mp4>
```

You can end the recording using Ctrl + C at any time. There's one caveat though, ADB can only record for a maximum period of 3 minutes. So, this is only useful if you want short recordings.

Similarly, you can also capture screenshots of your device with a simple command shown below-

```
adb shell screencap  
<path/filename.png>
```

The screenshot taken via ADB will not send a notification to the status bar of your device, but the file gets automatically saved in the provided location.



REBOOT YOUR DEVICE INTO BOOTLOADER, RECOVERY, FASTBOOT AND SIDeload

If you flash custom ROMs on your Android device often, you will possibly be tired of the arduous task of powering off your device and then pressing numerous keys in different sequences to boot your device into bootloader, recovery, fastboot or sideload. The commands to reboot your device into these modes are extremely simple-

```
adb reboot bootloader  
adb reboot recovery  
adb reboot sideload  
adb reboot fastboot
```

In addition to the tips and tricks we've mentioned in this Level Up, you can also transfer files back and forth between your PC and smartphone, install or uninstall applications, and much more with ADB commands. If rooting is not for you, ADB commands are a good way to gain more granular control over your Android devices. 

```
C:\Users\Ryzen\Downloads\platform-tools>adb shell wm density  
Physical density: 420
```

Check the DPI of your device before changing it