



Installing and Using MariaDB on Ubuntu

MariaDB is a popular database server today, primarily because of its good performance and compatibility with MySQL. This article gives a short tutorial on how to install and use MariaDB on an Ubuntu machine.

MariaDB is an open source database server that supports relational databases. The developers of MySQL have developed this database and guarantee that MariaDB is going to stay open sourced. This popular database server is part of most major cloud offerings today, and gives great importance to stability and performance. MariaDB developers believe it is very important for it to be compatible with MySQL...and that is yet another reason for its popularity.

MariaDB has recently added clustering techniques using the Galera cluster, and is also compatible with Oracle databases.

Let us now see how we can install and use MariaDB on an Ubuntu machine.

First, let us update our packages by running the following command, as shown in Figure 1.

```
sudo apt update
```

We can now install MariaDB. However, we first need to get the sudo permission by entering the following command:

```
sudo su
```

Now enter the following command to install the MariaDB server, as shown in Figure 2.

```
apt-get install mariadb-server
```

Sometimes you may not have what

is needed to install MariaDB. So it will give you the instructions to first get the requirements, and only then will it be installed.

Now let us see how we can look at the configuration of the MariaDB we installed. Use the command shown in Figure 3. You can then

```
jishnusaaurav@jishnusaaurav-IdeaPad-L340-15IRH-Gaming:~$ sudo apt update
[sudo] password for jishnusaaurav:
Hit:1 https://download.docker.com/linux/ubuntu bionic InRelease
Ign:2 http://dl.google.com/linux/chrome-remote-desktop/deb stable InRelease
Hit:3 https://linux.teamviewer.com/deb stable InRelease
Hit:4 http://dl.google.com/linux/chrome/deb stable InRelease
Hit:5 https://deb.nodesource.com/node_14.x bionic InRelease
Hit:6 http://dl.google.com/linux/chrome-remote-desktop/deb stable Release
Hit:7 http://in.archive.ubuntu.com/ubuntu bionic InRelease
Get:8 http://in.archive.ubuntu.com/ubuntu bionic-updates InRelease [88.7 kB]
Err:9 https://apache.bintray.com/couchdb-deb bionic InRelease
403 Forbidden [IP: 34.215.85.241 443]
Hit:10 http://packages.microsoft.com/repos/code stable InRelease
Ign:11 http://ppa.launchpad.net/couchdb/stable/ubuntu bionic InRelease
Hit:13 https://packages.microsoft.com/repos/ms-teams stable InRelease
Get:14 http://in.archive.ubuntu.com/ubuntu bionic-backports InRelease [74.6 kB]
Hit:15 http://downloads.metasploit.com/data/releases/metasploit-framework/apt lu
cid InRelease
Hit:16 http://ppa.launchpad.net/graphics-drivers/ppa/ubuntu bionic InRelease
Get:17 http://security.ubuntu.com/ubuntu bionic-security InRelease [88.7 kB]
Hit:18 http://ppa.launchpad.net/openshot.developers/ppa/ubuntu bionic InRelease
Get:19 http://in.archive.ubuntu.com/ubuntu bionic-updates/main amd64 DEP-11 Meta
data [293 kB]
Get:20 http://in.archive.ubuntu.com/ubuntu bionic-updates/universe amd64 DEP-11
```

Figure 1: Updating packages

```
jishnusaaurav@jishnusaaurav-IdeaPad-L340-15IRH-Gaming:~$ sudo apt-get install mari
adb-server
[sudo] password for jishnusaaurav:
Reading package lists... Done
Building dependency tree
Reading state information... Done

mariadb-server is already the newest version (1:10.1.48-0ubuntu0.18.04.1).
The following packages were automatically installed and are no longer required:
  libevent-core-2.1-6 linux-hwe-5.4-headers-5.4.0-73
  linux-hwe-5.4-headers-5.4.0-74 linux-hwe-5.4-headers-5.4.0-77
  linux-hwe-5.4-headers-5.4.0-80 linux-hwe-5.4-headers-5.4.0-81
  linux-hwe-5.4-headers-5.4.0-84 linux-hwe-5.4-headers-5.4.0-86
Use 'sudo apt autoremove' to remove them.
0 upgraded, 0 newly installed, 0 to remove and 75 not upgraded.
N: Ignoring file 'nvi' in directory '/etc/apt/sources.list.d/' as it has no file
name extension
```

Figure 2: MariaDB server Installation

```
jishnusaaurav@jishnusaaurav-IdeaPad-L340-15IRH-Gaming:~$ sudo vim /etc/mysql/mariadb.conf.d/50-server.cnf
```

Figure 3: Command to open the configuration file