

* mbuf says "Hello, World!"

4. `/whois nickname` provides useful information for a user. For example:

```
/whois mbuf
```

```
* [mbuf] (--shakthi@123.123.123.123): Shakthi Kannan
* [mbuf] #guile #scheme ##linux-india #stumpwm #guix #dgpplug
#lisp #emacs
* [mbuf] kornbluth.freemove.net :Frankfurt, Germany
* [mbuf] is connecting from *@123.123.123.123 123.123.123.123
* [mbuf] idle 00:41:52, signon: Thu Sep 3 20:36:52
* [mbuf] is logged in as mbuf
* [mbuf] End of WHOIS list.
```

5. `/msg nickname` is used to send a private message to a nickname and to start a private conversation.
6. An example list of commands from `/help` are shown below:

ADDBUTTON	ALLCHAN	ALLCHANL	ALLSERV	AWAY
BACK	BAN	CHANOPT	CHARSET	CLEAR
CLOSE	COUNTRY	CTCP	CYCLE	DCC
DEBUG	DEHOP	DELBUTTON	DEOP	DEVOICE
DISCON	DNS	ECHO	EXEC	EXECCONT
EXECUTILL	EXECSTOP	EXECWRITE	FLUSHQ	GATE
GETFILE	GETINT	GETSTR	GHOST	GUI
HELP	HOP	ID	IGNORE	INVITE
JOIN	KICK	KICKBAN	KILLALL	LAGCHECK
LASTLOG	LIST	LOAD	MDEHOP	MDEOP
ME	MENU	MKICK	MODE	MOP
MSG	NAMES	NCTCP	NEWSERVER	NICK
NOTICE	NOTIFY	OP	PART	PING
QUERY	QUIT	QUOTE	RECONNECT	RCV
SAY	SEND	SERVCHAN	SERVER	SET
SETCURSOR	SETTAB	SETTEXT	SPLAY	TOPIC
TRAY	UNBAN	UNIGNORE	UNLOAD	URL
USELECT	USERLIST	VOICE	WALLCHAN	WALLCHOP

User defined commands are:

ACTION	AME	ANICK	AMSG	BANLIST
CHAT	DIALOG	DMSG	EXIT	GREP
J	KILL	LEAVE	M	ONOTICE
RAW	SERVHELP	SPING	SQUERY	SSLSERVER
SV	UMODE	UPTIME	VER	VERSION
WALLOPS	WII			

Plugin defined commands are:

UNLOAD	UNLOAD	LOAD	PY	LOAD
RELOADALL	SOURCE	TCL	RELOADALL	UNLOADALL
PL_RELOAD	RELOAD	UNLOAD	LOAD	TIMER

Type the `/HELP <command>` for more information, or `/HELP -1`

7. `/quit` is used to disconnect and exit from IRC.
8. `/join #channel` is used to join a channel. For example:

```
/join #guix
```

9. `/nick newnickname` changes your nick to `newnickname`.

Suppose you wish to move away from the computer, you can change your nick to `nick/away` or `nick/phone`.

10. `/part` is used to leave a channel.

Using `rcirc`

If you are using a recent GNU/Linux distribution, you should already have `rcirc` as part of GNU Emacs. You can simply start it by typing `M-x rcirc` from inside Emacs. The 'M' key represents the Meta key, which is usually mapped to the 'Alt' key. After `rcirc` connects to the IRC server, you can use `'/nick'` to change your nickname, register (only the first time) your `nick`, identify yourself, join channels, and start chatting! Since everything is a buffer in GNU Emacs, each channel is a separate buffer. For example, `#emacs@irc.freemove.net` is the `#emacs` IRC channel. All your basic buffer navigation commands will work just like they would on a file!

Some basic `rcirc` commands

The `rcirc` commands for the above mentioned IRC commands are given in Table 1.

Table 1

IRC	rcirc
<code>/list</code>	<code>rcirc-cmd-list</code>
<code>/msg NickServ</code>	<code>rcirc-authenticate</code>
<code>/me</code>	<code>rcirc-cmd-me</code>
<code>/whois</code>	<code>rcirc-cmd-whois</code>
<code>/msg nick</code>	<code>rcirc-cmd-msg</code>
<code>/help</code>	<code>/help</code>
<code>/quit</code>	<code>rcirc-cmd-quit</code>
<code>/join</code>	<code>rcirc-cmd-join</code>
<code>/nick</code>	<code>rcirc-cmd-nick</code>
<code>/part</code>	<code>rcirc-cmd-part</code>

`~/emacs`

GNU Emacs is an extensible editor. There are a number of locations where Emacs checks for custom configurations before launching the editor. These are: `~/emacs`, `~/emacs.el` and `~/emacs.d/init.el`. The start-up files can be customised, and their locations can also be changed. There are a number of ways to organise and manage your Emacs configuration. Until we get to learn Emacs Lisp, and customise Emacs as a project, we will use `~/emacs` for all our user-specific customisation.