



Powered By

facebook

www.facebook.com/linuxforyou



Vigneshwar R Cool:

I installed Ubuntu Server in the main disk which has partitions in it and it also contains Windows 7 in it but the installation did not affect the windows file but later I removed Ubuntu from my system Now when I boot the system after the bios screen some thing like this flashes:

```
...error: no such device: 8c950-c0684c1f-9ca4-4abd32325df0.grub rescue>
```

So please help me in getting back my previous Windows7 boot loader rather than this one.

Like · comment



Vigneshwar R Cool: Sorry, but I got the solution to my problem. Let me share it with you. boot another Windows installation cd and select the command prompt and type the following command
>bootrec/fxldr. r type > bootrec? or more options



Phani Kumar Veluturi: Hi! This link might help: <http://www.howtogeek.com/howto/32523/how-to-manually-repair-windows-7-boot-loader-problems/>



Mani Kiran:

How can we extend the partition size in Fedora 16? It is unable to extend its size automatically, and consequently now I have lost my accessibility to the data (because of low disk space). Please help with the correct solution

Like · comment



Phani Kumar Veluturi: If you are using lvm that would be easy to extend or reduce.



Back Track:

How do we upgrade to Ubuntu 11.10?

Like · comment



Agnel Vittu: Hope this link serves your purpose, <http://www.ubuntu.com/download/ubuntu/upgrade>



Back Track: Thanks!



Suman Gangopadhyay:

I installed the CentOS 6 server edition with all the server stuffs, but I didn't find the dhcpd daemon. How could I then configure my CentOS DHCP server?

Like · comment



Phani Kumar Veluturi: You can install the dhcp server package "yum install dhcp". That might help.



Vaibhav Kadam:

What is the difference between ext 4 and ext 3?

Like · comment



Santhosh Ram: File system is nothing but a method for an Operating System to keep and organise Data (files and folders) in a Partition/Drive. EXT2, EXT3 and EXT4 are the Linux File systems. The latest is the EXT4 and was introduced on 2008. The former EXT2 is the older one and has some drawbacks. You can check out this link to find out more, <http://www.thegeekstuff.com/2011/05/ext2-ext3-ext4/>.



Mrutyunjaya Gadanayak: In ext4 you don't need to run fsck on every crash.



Dushan Madushanka:

I want to know how to connect Huawei E153 to CentOS. Please help me!

Like · comment



Phani Kumar Veluturi: Install wvdial package, connect the device after running "wvdial-conf". Build a configuration file for wvdial. Edit the configuration file with the details given below, /etc/wvdial.conf
Username =
Password =
Phone = #777
After that run "wvdial" command to dial. Once connection is established. You will receive the IP and DNS address. Add it in /etc/resolv.conf file. You can then enjoy your internet :).