

Figure 3: Welcome screen



Figure 4: Preparing to install

OS, you may be asked to input your *sudo* password.

This step is essential to do a permanent install of the Linux/Ubuntu desktop into the other USB (Sony 16 GB). In just a few minutes, the temporary OS installation will be completed. The temporary OS is now installed in the Sandisk 8 GB USB.

**Step 2:** Insert the Sandisk USB into the laptop or computer and reboot. While rebooting, press F12 (or a similar key) for booting into the USB. For many laptops, you need to press F12 to boot from the USB; on some hardware, pressing Shift+Del keys works. Use Google to find out the USB boot key if your hardware is not USB bootable, using these keys.

**Step 3:** You will see a few options after rebooting. Choose the option as seen in Figure 2, and then hit *Enter*.

From this step onward, the procedure followed is a technique that I have developed for embedding a personal PC into a USB; so you probably will not find this anywhere on the Internet.

**Step 4:** Keep hitting the Continue button when you see a screens like what's shown in Figure 3 & 4. Continue till you see the *Installation Type* screen.

**Step 5:** This is a critical step. Choose the option that can be seen in Figure 5. Please do not make any mistakes here, or you could lose the contents of the laptop or computer on which you are running this step.

**Step 6:** Create two partitions on your Sony USB. The first one is *ext 4* and the second is *swap*. See Figure 6. Please ensure that you select the Sony USB for *Device for boot loader installation* and select the Sony USB *ext 4* partition before clicking the *Install Now* button.

**Step 7:** Follow the usual steps of installation by clicking




Figure 5: Installation type




Figure 6: Creating partitions




Figure 7: Location options

*Continue/Next*. See Figures 7 and 8.

**Step 8:** When asked about User creation, input details similar to what is seen in Figure 9.

**Step 9:** Follow the other screen by clicking *Continue/Next* till you see Figure 10. Congratulations! You now have your OS ready to be carried around in your pocket, ready to be run anywhere!

You can insert your USB PC into any computer or laptop and do a USB boot (remember, you need to press F12 or a similar key to boot from the USB). You will see the screen