



TIPS & TRICKS

Using 'vi' commands on your terminal

 Using 'vi' commands while working on the terminal is a good work enabler. To set your terminal to 'vi' mode, you need to use the following command:

```
set -o vi
```

Now you can use the command mode and the insert mode of 'vi' while working on the terminal.

—Dipjyoti Ghosh,
dipjyoti.ghosh@gmail.com

Get your IP address

 Here is a one line command to fetch all the IP addresses (except *localhost*) of your computer:

```
# ifconfig | grep "inet addr:" | awk '{print $2}' | grep -v  
'127.0.0.1' | cut -f2 -d:
```

Note: Use the above command as the root user.

—Balkaran Brar,
balkaran.brar@gmail.com

Make your system speak for you!

 You can make your system speak for you by using the *Speech Synthesizer* command normally available in Ubuntu and many other distributions of Linux.

To do so, issue the following command:

```
# espeak "hello how are you"
```

You will hear a voice speaking for you.

To change the pitch of the voice, you can issue the following command in the format shown:

```
# espeak -p 80 "hello how are you"
```

...(default being 50)

Issuing the following form of the command will control the speed of the speech, in terms of words per minute:

```
# espeak -s 80 "hello how are you"
```

There are more interesting options available in the man pages.

—Sanjay Goswami,
sanjaygoswamee@gmail.com

Measuring the network throughput between two Linux systems

 *Iperf* is a tool that measures the bandwidth and the quality of a network link. It can be installed very easily on any Linux system. One host must be set as the client and the other one as the server. Make sure that *iperf* is installed on both systems. If it is not installed, then use your package manager to install it before trying this tip.

Now run *iperf* on one of the Linux systems as the server, as shown below:

```
linux-erv3:/home/test/Desktop # iperf -s
```

```
.....  
Server listening on TCP port 5001
```

```
TCP window size: 85.3 KByte (default)  
.....
```

Go to the second Linux system and run *iperf -c <host_name or server_ip>* as the client:

```
linux-6bg3:~ # iperf -c 192.168.1.100
```

```
.....  
Client connecting to 192.168.1.100, TCP port 5001
```