

Now, add the following:

```
/dev/sda6 /backup ext3 defaults,acl 0 0
```

Save and quit the text editor.

Then remount that partition:

```
# mount -o remount,acl /dev/sda6
```

Now, try setting the *acl* for that directory.

—Nebu Pulickal, nebupulickal@gmail.com

Create your own Debian repository and save bandwidth

You can create your own Debian repository from an installed Debian or Ubuntu system. This can help you to save bandwidth and your time.

To do this, you need the package *dpkg-dev*. If not already installed, you can install it from the synaptic package manager.

Now, create a directory. As an example, let's name it 'my_repo'. This directory will be the root of your repository. Under this directory, create a directory named 'binary'

After that, copy '.deb' files from '/var/cache/apt/archives/' into the 'binary' directory.

Now cd to the 'my_repo' directory and run the following command:

```
dpkg-scanpackages binary /dev/null | gzip -9c > binary/  
Packages.gz
```

Successful completion of the above command will create your packages list.

Your repository is ready. You can save the entire 'my_repo' directory into any other system, change the '/etc/apt/sources.list' file, and add the path of the 'my_repo' directory to use this offline repository.

Add the following in the source.list:

```
deb file:///home/boss/my_repo binary/
```

If you don't have an Internet connection you can comment out other lines. Then reload the repository list and check.

—Kousik Maiti, kousikster@gmail.com

List the files in an 'rpm' package without installing it

To list the files available in an 'rpm' package without installing it, run the following command:

```
# rpm -qlp "Package_name.rpm"
```

Where:

'q' stands for 'query'

'l' for 'listing'

'p' for 'package'

and 'Package_name.rpm' is the name of the 'rpm' package for which you want to know the details.

—Vikash Kumar Jha, v4evervikash@gmail.com



Set up two different IP addresses on a single network interface controller (NIC)

The example given below is based on a wired Ethernet device.

Step 1: The settings for the first IP address should be as specified below:

```
$ cat /etc/sysconfig/network-scripts/ifcfg-eth0
```

```
DEVICE=eth0  
BOOTPROTO=static  
BROADCAST=192.168.99.255  
IPADDR=192.168.1.155  
NETMASK=255.255.252.0  
NETWORK=192.168.1.0  
ONBOOT=yes
```

Step 2: Add the set of parameters given below to the 'ifcfg-eth0:1' file to set up the second IP address.

```
$ cat /etc/sysconfig/network-scripts/ifcfg-eth0:1
```

```
DEVICE=eth0:1  
BOOTPROTO=static  
BROADCAST=192.168.99.255  
IPADDR=192.168.1.182  
NETMASK=255.255.252.0  
NETWORK=192.168.1.0  
ONBOOT=yes
```

Now, you can ping and check both IP addresses.

—Suyog patil, suyogsei48@gmail.com

END

Share Your Linux Recipes!

The joy of using Linux is in finding ways to get around problems—take them head on, defeat them! We invite you to share your tips and tricks with us for publication in LFY so that they can reach a wider audience. Your tips could be related to administration, programming, troubleshooting or general tweaking. Submit them at www.linuxforu.com. The sender of each published tip will get an LFY T-shirt.