

1. Download the latest FreeNAS ISO from the freely available online resources such as <http://www.freenas.org/download-releases.html>.
2. Create a virtual machine.
3. Configure it.
4. Boot into the newly created virtual machine with FreeNASiso.
5. Follow the steps in the installation procedure to install FreeNAS (as shown in the screen shots later).
6. Once installed, you will find a very easy and user-friendly command line interface to do the basic administrator stuff or you can also use the GUI Web portal for this.
7. Create your own share and you are done.

Steps to install and configure FreeNAS

1. Create a virtual machine with a virtual disk with a minimum of 2 GB.
2. Remember to create one more virtual disk of appropriate size, as FreeNAS doesn't allow sharing of the disk on which the OS is installed.
3. Please refer to Figure 7 for more information.
4. In the storage section, only attach the FreeNAS ISO image.
5. Make sure you have at least one network interface configured for the virtual machine.
6. Now start the virtual machine, and in the boot screen select the option to boot through the CD ROM (see Figure 1).
7. Most of the installation is very simple and needs very little manual intervention.
8. Once booted, you will find a boot screen with options asking you what you would like to do with the current session. Select Option 1 'Install/Upgrade' (see Figure 2).
9. In the next screen, the installer will ask you to select the disk on which you want to install the FreeNAS operating system (see Figure 3).
10. The next screen will give you a general message stating the consequences of the operation you are doing. Select the option 'Fresh Install' (see Figure 4).
11. The next screen will give you another warning message about formatting the disk drive selected for installation; select 'Yes' and proceed (see Figure 5).
12. That's it! In the blink of an eye, you will see another message saying your FreeNAS OS has been installed, and to reboot the system (see Figure 6).
13. When booted again to the installed OS, you will find a console with multiple options available for various configurations, along with which you will see the IP address mentioned to log in to the Web GUI to do all kinds of storage management tasks (see Figure 8).
14. Use the mentioned IP address in the console to log in to the Web GUI (see Figure 9).
15. On the Web GUI, you will find it easy to understand and use the menu options. You can go through all of them and when clicked, the results will be self-explanatory.




Figure 1: Virtual box welcome screen, listing options to boot from




Figure 2: FreeNas select operation screen, choose Install/Upgrade

