

Installing Redis

Redis can be installed using two methods: via apt-get or by downloading the source code as a tarball file and compiling it yourself. Here's a brief overview of both methods.

Using apt-get: This is the simpler method if you are using a Debian-based distribution like Ubuntu. Using apt-get handles dependencies automatically and configures Redis as a service, allowing it to start automatically on boot. Here's how you can install it.

- **For Ubuntu:**

```
sudo apt-get update
sudo apt-get install redis-server
```

After installation, ensure that the Redis server is running:

redis-server

From the tarball (source code): If you prefer to install the latest version or need a specific version that's not available in the repository, you might want to compile Redis from source. Here's how you can do it.

Download the redis tar and extract it, as shown in Figure 1.

After extracting, open the redis-stable folder and use the command *make* as shown in Figure 2.

Run the Redis server as shown in Figure 3.

To interact with Redis from a Python application, install the `redis-py` library—a Python client for Redis.

```
pip install redis
```

```
(venv) ht@ext:~/sambashare/intent_classification/redis_install/redis-stable$ make
cd src && make all
make[1]: Entering directory '/home/ht/sambashare/intent_classification/redis_install/redis-stable/src'
cc Makefile.dep
rm -rf redis-server redis-sentinel redis-cli redis-benchmark redis-check-rdb redis-check-aof *.o *.gcda *.gcno *.gcov redis.info lcov.html Makefile.dep
rm -f adlist.d quicklist.d ae.d anet.d dict.d server.d sds.d zmalloc.d lzf.c.d lzf.d.d pqsort.d zipmap.d shal.d ziplist.d release.d networking.d util.d
et.d t_zset.d t_hash.d config.d aof.d pubsub.d multi.d debug.d sort.d intset.d syncio.d cluster.d crc16.d endianconv.d slowlog.d eval.d bio.d rio.d ram
nel.d notify.d setproctitle.d blocked.d hyperloglog.d latency.d sparkline.d redis-check-rdb.d redis-check-aof.d geo.d lazyfree.d module.d evict.d expir
he.d rax.d t_stream.d listpack.d localtime.d lolmut.d lolmut5.d lolmut6.d acl.d tracking.d socket.d tls.d sha256.d timeout.d setcpuaffinity.d monotonic
ipt.d functions.d function_lua.d commands.d strl.d connection.d unix.d logreqres.d anet.d adlist.d dict.d redis-cli.d zmalloc.d release.d ae.d redisass
_common.d mt19937-64.d strl.d cli_commands.d ae.d anet.d redis-benchmark.d adlist.d dict.d zmalloc.d redisassert.d release.d crcspeed.d crc64.d siphast
h
(cd ../deps && make distclean)
make[2]: Entering directory '/home/ht/sambashare/intent_classification/redis_install/redis-stable/deps'
(cd hiredis && make clean) > /dev/null || true
(cd linenoise && make clean) > /dev/null || true
(cd lua && make clean) > /dev/null || true
(cd jemalloc && [ -f Makefile ] && make distclean) > /dev/null || true
(cd hdr_histogram && make clean) > /dev/null || true
(cd fpconv && make clean) > /dev/null || true
(rm -f *.make~)
make[2]: Leaving directory '/home/ht/sambashare/intent_classification/redis_install/redis-stable/deps'
(cd modules && make clean)
make[2]: Entering directory '/home/ht/sambashare/intent_classification/redis_install/redis-stable/src/modules'
rm -rf *.xo *.so
make[2]: Leaving directory '/home/ht/sambashare/intent_classification/redis_install/redis-stable/src/modules'
(cd ../tests/modules && make clean)
make[2]: Entering directory '/home/ht/sambashare/intent_classification/redis_install/redis-stable/tests/modules'
rm -f commandfilter.so basics.so testrb.so fork.so infotest.so propagate.so misc.so hooks.so blackkeys.so blackbackground.so scan.so datatype.so d
tkeys.so getchannels.so test_lazyfree.so timer.so defragtest.so keyspecs.so hash.so zset.so stream.so mallocsize.so aclcheck.so list.so subcommands.so

```

Figure 2: Using *make* to install Redis

```
(venv) ht@ext:~/sambashare/intent_classification/redis_install/redis-stable/src$ redis-server
15434:C 13:10:17.773 # 000000000000 Redis is starting 000000000000
15434:C 13:10:17.773 # Redis version=7.0.11, bits=64, commit=00000000, modified=0, pid=15434, just started
15434:C 13:10:17.773 # Warning: no config file specified, using the default config. In order to specify a c
15434:M 13:10:17.773 * Increased maximum number of open files to 10032 (it was originally set to 1024).
15434:M 13:10:17.773 * monotonic clock: POSIX clock_gettime
```



```
Redis 7.0.11 (00000000/0) 64 bit

Running in standalone mode
Port: 6379
PID: 15434

https://redis.io
```

Figure 3: Running Redis server