



Figure 8: The Relax-and-Recover official page

- Physical-to-physical (P2P)
- Virtual-to-virtual (V2V)
- Assorted virtualisation technologies
- Support for assorted boot media
 - USB
 - PXE
 - eSATA
 - ISO
 - OBDR/bootable tape
- Support for different transport protocols
 - HTTPS
 - HTTP
 - SFTP
 - NFS
 - FTP
 - CIFS (SMB)
- Extensive and exhaustive implementation for disk layout
 - SWRAID
 - LVM
 - HWRAID
 - multipathing
 - iSCSI
 - DRBD
 - LUKS (encrypted partitions and file systems)
- Support for third party technologies for backup
 - EMC NetWorker (Legato)
 - HP DataProtector
 - CommVault Galaxy
 - IBM Tivoli Storage Manager (TSM)
 - Symantec NetBackup
 - Bacula
 - SEP Sesam
 - Bareos
 - Duplicity/Duply
- Assorted methods for internal backup
 - rsync
 - tar
- Multi-phase disk layout recovery
- Effective and easy monitoring
- Integration with high performance scheduler

Working with the Rear tool: You can clone Relax-and-Recover from GitHub as follows:

```
$ git clone https://github.com/rear/rear.git
$ cd rear/
```

You can also prepare your own USB media. Relax-and-Recover will 'own' the device in the following example.

```
This will destroy all data on that device.
$ sudo usr/sbin/rear format /dev/sdb
```

```
Relax-and-recover confirm to format the device -
Yes / No
```

The device has been labeled REAR-XXXX by the "format" workflow.

```
Edit "etc/rear/local.conf" configuration file:
$ cat > etc/rear/local.conf <<EOF
OUTPUT=USB
```

```
BACKUP=NETFS
```

```
BACKUP_URL=usb:///dev/disk/by-label/REAR-000
EOF
```

Now, create a rescue image.

```
$ sudo usr/sbin/rear -v mkrescue
```

```
Using log file: /home/myuser/tmp/quickstart/rear/
var/log/rear/rear-fireflash.log
Creating disk layout
Creating root filesystem layout
WARNING: To login as root via ssh you need to
setup an authorized_keys file in /root/.ssh
Copying files and directories
Copying binaries and libraries
Copying kernel modules
Creating initramfs
Writing MBR to /dev/sdb
Copying resulting files to usb location
```

Reboot the system to boot from the USB device.
Initiate the backup as follows:

```
$ sudo usr/sbin/rear -v mkbackup
```



By: Dr Gaurav Kumar

The author is the MD of Magma Research and Consultancy Pvt Ltd, Ambala. He is associated with a number of academic institutes, where he delivers lectures and conducts technical workshops on the latest technologies and tools. You can contact him at kumargaurav.in@gmail.com or www.gauravkumarindia.com.