

System requirements

Processor	1. Pentium III: Minimum 900MHz CPU, or equivalent 2. Pentium IV: Its equivalent or higher
Operating system	Both 32-bit and 64-bit versions of the following: 1. Windows 8 2. Windows 7 3. Windows Vista 4. Windows XP 5. Windows 2000
Memory/OS	1. Windows 8: 2GB minimum; 4GB or higher recommended 2. Windows 7: 1GB minimum; 2GB or higher recommended 3. Windows Vista: 1GB minimum; 2GB or higher recommended 4. Windows XP: 512MB minimum; 1GB or higher recommended 5. Windows 2000: 256MB minimum; 512MB or higher recommended
Others	1. 800 x 600 px and 256-colour display minimum; 1024 x 768 px 32-bit colour display recommended 2. Two-button mouse minimum; three-button mouse or wheel mouse recommended 3. Minimum 500MB free disk space 4. Optional graphics accelerator card 5. Internet Explorer version 5, its equivalent or higher

comes with a large collection of pre-defined graphical representations of standard components in both schematic and PCB layout view. The user can update, customise or enhance the components of the library using the Library Editor tool. The components also contain details like packaging information, thermal parameters and link to simulation modules.

Mixed Mode and EDSpice simulators. Simulators let you test the performance of a circuit for various DC operating points for a range-applied signal over output levels, supply voltages and temperatures. EDWinXP provides a Mixed Mode Simulator (the system's native circuit level analyser) and an EDSpice Simulator (full implementation of SPICE standards).

Layout Editor. This lets you create and edit PCB layout for the designed schematic. It also allows you to begin layout with a pre-existing schematic, edit existing layouts or capture the

design directly in PCB layout mode. Operations like placing components, renumbering of components, routing and error check are automated. 3D Board Viewer and 3D Trace Viewer are the other features.

Fabrication Output Manager. This program is used to generate manufacturing output files for Photoplotter, NC Drill, etc. NC Drill data can be generated in Excellon format with or without tool movement optimisation. Users also have the option to create drill templates that can be printed or saved in Gerber format for photoplotting. It is possible to insert dimensions of various mechanical drawings. PCB assembly output is generated in IPC-355 format and bare board testing output is obtained in IPC-356A format. You can also export the entire database in GenCAM format. Users can generate disk files containing bill of material and generic data for pick-and-place machines. The tool supports RS-274D and extended RS-274X Gerber ASCII formats. Integrated Gerber ASCII file viewer enables the user to verify artworks before sending them for plotting and manufacturing.

Features

EDWinXP is rich in features and the added features in each revised version are incorporated from the customers' feedback and suggestions. The key features are:

Front and back annotate. Designs can be captured in Schematic Capture or Layout Editor. The design created using Layout Editor is back annotated to the Schematic Editor and the one created using Schematic Editor is front annotated to the Layout Editor.

Microcontroller kit. It comes with a microcontroller kit that mimics the functionality of 8051, AVR, PIC and Motorola microcontrollers. Moreover, editing and compilation of programs in C and Assembly languages and debugging the code in real time is possible. The kit also contains series of models like memory, 7-segment displays, series/parallel pattern generators and interrupt generators for generating parallel and serial data patterns and

asynchronous hardware interrupts.

Filter designer. EDWinXP offers automated filter designing where you can choose the filter type, enter the output frequency and quality range, and the program calculates the parameters and generates schematic. This can be imported to PCB layout format.

Autoplacing and autorouting. Autoplacing of components in the schematic layout is possible with Schematic Editor. The autoplacing parameters and design rules can be set by the customer. Autorouter can be executed in PCB layout with default parameters or user-defined parameters using Arizona Autorouter in EDWinXP.

Analysers. Another feature is the different types of analysers that help a user check the integrity and correctness of layout design. The electromagnetic analysers—field analyser and signal integrity analyser—are used to inspect electromagnetic effect on the board, and thermal analyser lets you examine the thermal hotspots on the board.

And much more! EDWinXP has option to get a 3D view of the component packages. VHDL Editor lets you automate project creation from VHDL source. With the project version control you can keep track of the changes made to the projects. The entire design details are stored in an integrated database that can be accessed simultaneously by the Schematic Editor, Layout Editor, Simulators and Fabrication Manager. This program offers backward compatibility to older DOS-based design files. VHDL/Truth Table to

Installation guide

1. Unzip file EDWinXP190.ZIP to a temporary folder.

Note: Temporary folder name should not have spaces in between or number of characters more than 8. This will lead to error messages 'Install list missing or invalid' or 'Command Line Invalid'.

2. The unzipped folder EDWinXP190 has executable file Setup.exe. Double-click this file (or right click on it and select 'Run as administrator' from the drop-down menu) to launch the installation wizard.

3. In the installation window that appears, select 'Install EDWinXP Evaluation' and continue with the installation procedure.