


Connect to/Disconnect from a Server

To Connect to a Server

1. Go to the Main Menu and select: **File > Connect...**



2. The system will display the standard **Process Builder login box**. Choose a DELMIA Apriso server from the **Server** list, or press the  button to add, change, or remove servers from the list (see [Manage Available Server Connections](#) for more information).



The image shows a login dialog box for DELMIA Apriso 2025 Process Builder. On the left is a large blue stylized logo. On the right, the title 'DELMIA Apriso 2025 Process Builder' is displayed. Below the title are three input fields: 'Server', 'Login', and 'Password'. The 'Server' field has a dropdown menu icon on its right. Below the 'Login' field is a 'Remember password' checkbox. At the bottom are three buttons: 'Log In' (blue), 'Cancel' (grey), and 'Help' (blue). Below these buttons is a horizontal line with 'OR' in the center, and two links: '3DPassport' and 'OpenID Connect'.

3. Enter the appropriate **Login** and **Password** for the server chosen. Select the **Remember password** box to save the password for future logins.

It is possible to disable the **Remember password** check box with use of the "AllowRememberPassword" key located in the "SystemServices.Security" section of the Central Configuration file (for details see [Central Configuration Documentation](#)).

4. Click the **Log In** button to connect to the chosen server. If the system successfully establishes a connection, the dialog box will disappear, and the Connected (🔌) icon along with the server and login information will be displayed in the Status bar (and depending on what was set in Options, the Entity Manager window may also appear). If the connection is unsuccessful, the system will show an error message and display the dialog box once more.
5. Alternatively, you can choose another authentication method based on the DELMIA Apriso configuration:
 - ▶ When 3DPassport Authentication is enabled, click the **3DPassport** option and provide your Username or email and Password in the 3DPassport login window:



3DPassport

 Username or email

 Password

Log in

English

[Close](#)

Depending on the 3DPassport configuration, logging in with email may not be supported.

- ▶ When OpenId Connect Authentication is enabled, click **OpenID Connect** option and provide your credentials. The authentication method depends on the external identity provider configuration.

Some features of Process Builder may not be available, depending on the [Security Roles](#) assigned to the user. For more information on Security Roles, refer to the [Role and Skill Configuration Help](#).

To Disconnect from a Server

Go to the Main Menu and select: **File > Disconnect**

