

Entity Status Types

A color-code is used to indicate the status of an entity.

A default revision of entity has an overlay indicator in the upper-right corner of the icon – .

Entity Status Descriptions

Status	Color	Description
Active	       	An entity that has been successfully tested in the Prototype status can be released to the Active status. In the Active status, the entity can be executed in runtime. It is possible to enter test values (e.g., in the User Formula and SQL Query Editors, Grid Business Control, and HTML Layout Editor) without saving changes, but no further modifications can be made. If an entity is released to the Active status, it cannot be modified in the same revision – a new revision must be created. The only exception is the ability to edit specific properties of Screens and Views that are in the Active status, but this requires additional configuration. An entity cannot be moved back from Active to Design in Progress.
Prototype	       	This status is used for testing purposes, before releasing an entity to Active status (which cannot be changed back to Design in Progress). It enables executing entities in Function Interpreter and moving them back to Design in Progress status without creating new revisions. Prototype status may be changed back to Design in Progress or Development in Progress or released to Active status.
Development in Progress	       	This status is used while working on the entity and its development is in progress. Entities in Development in Progress status cannot be moved with the use of Global Process Manager.
Design in Progress	       	Every new entity is created in Design in Progress status. In this status the entity can be edited and modified, but cannot be executed in the Function Interpreter. Design in Progress status may be changed to Prototype, Active, or Cancelled. You can go back to Design in Progress status only from Prototype status.
On Hold	       	An entity can be put on hold (e.g., if it is faulty). On Hold status may be changed back to Active status. Status change from Active to On Hold is impossible for DFCs that are deployed without design data.

Cancelled		If the entity is defective or no longer needed, its status can be changed to Cancelled from Design in Progress, Prototype, Active, or On Hold status. A cancelled entity revision cannot be default if other revisions of this entity exist. Cancelling an entity cannot be undone, but some functionalities are still available for cancelled entities. For example, you can duplicate entities, move DFCs, screens, layouts, and views, and add processes and operations to GPM modules. Cancelling a DFC that is linked by revision to other non-cancelled entities might cause unexpected system behavior. A warning message informs about parent entities. Unlink this entity from any parent entity before cancellation.
Compiling in Process		A temporary status that occurs between status changes.

Valid Status Changes

You will notice that not all statuses will be available at once. This is because a certain sequence needs to be followed.

For more information on status change, see [Change the Status of an Entity](#).

From \ To	Design in Progress 	Prototype 	Development in Progress 	Active 	On Hold 	Cancelled 
Design in Progress 	N/A	✓	✓	✓	✗	✓
Prototype 	✓	N/A	✓	✓	✗	✓
Development in Progress 	✓	✓	N/A	✓	✗	✓
Active 	✗	✗	✗	N/A	✓	✓
On Hold 	✗	✗	✗	✓	N/A	✓
Cancelled 	✗	✗	✗	✗	✗	N/A

Compilation Status

Each entity has a compilation status (visible in the [Entity Manager](#) column). There are two types of compilation status:

- **Compiled** – the entity was successfully regenerated during a database upgrade, its status was successfully changed to Prototype or Active, or it was successfully built

- ▶ **Regeneration failed** – the entity was not successfully regenerated during a database upgrade (the Function Interpreter does not run Process or DFC in this status)