

Input Source: Session Variable

For more information on the general properties available for all inputs, see the [Input Properties](#) topic.

Properties

General

Name

Input1

Description

Data Type

Char

☒ Char

☐ Integer

☐ Decimal

☐ Boolean

☐ DateTime

☐ Complex

☒ Scalar

☐ List

☐ List (Iterate)

☐ List (Duplicate)

☒ Use Source Value Copy

Input Source

Session Variable

System Variables

(not set)

Session Variables

(not set)

External Inputs

(not set)

When you select a [session variable](#) as an input source, the input properties display the system variables and session variables fields.

Field	Description
System Variables	All the variables that are defined in the system and populated with context information (for example, EmployeeID or WipOrderNo). When one is chosen, the session system name field is automatically populated. The deprecated variables are never populated with values other than the default. The following predefined variables are available: ▶ Alert ID (AlertID) – deprecated ▶ Application Address (AppAddress) ▶ Client Screen Framework (ClientSF) ▶ Current Local Date/Time (CurrentLocalDateTime) ▶ Current Task ID (CurrentTaskID) – deprecated ▶ Current UTC Date/Time (CurrentUTCDateTime) ▶ DFC Code (DFCCode) ▶ DFC Revision (DFCRevision)

	▶ DFC Revision ID (DFCRevisionID) ▶ Employee ID (EmployeeID) ▶ Employee Number (EmployeeNo) ▶ Equipment ID (EquipmentID) ▶ Facility (Facility) ▶ Job ID (JobID) ▶ Language ID (LanguageID) ▶ Null Decimal (NullDecimal) ▶ Operation Sequence Number (OprSequenceNo) – deprecated ▶ Platform (Platform) ▶ Process ID (ProcessID) – deprecated ▶ Process Operation ID (ProcessOperationID) – deprecated ▶ Process Revision (ProcessRevision) – deprecated ▶ Reason Code (ReasonCode) – deprecated ▶ Screen ID (ScreenID) ▶ Step Sequence Number (StepSequenceNo) ▶ Task ID (TaskID) – deprecated ▶ Theme (Theme) ▶ Translation Mode (TranslationMode) ▶ View ID (ViewID) ▶ Web Address (WebAddress) ▶ WIP Order Number (WIPOrderNo) – deprecated ▶ WIP Order Type (WIPOrderType) – deprecated ▶ Work Center (WorkCenter) – deprecated
Session Variables	All the variables that are defined by the process author and available within the open DFC. When one is chosen, the session variable name field is automatically populated.
External Inputs	Enabled when the external input exists in a DFC. It gives the possibility to choose the external input that can be used within a DFC. The list contains the external inputs that are defined on the DFC Interface tab .

When using an output defined within one step, choose an output from the previous function and not a session variable.