

Layout: General Tab

The Layout **General** tab options are different depending on whether the Layout has Panels linked or not.

General Tab of a Layout without Panels

Properties

General

Name

Layout

Revision

REV.001.000

☒ Default Revision

Description

Layer type

☒ Background☐ Panel☐ Sub-Panel☐ Transparent (show content only)

Style

CSS Classes

Inline Style

Default Header

Name

PortalDefaultHeader

Revision

APR.002.001

Version

1.0.0.1

Edit Mask...

Version host

General Tab of a Layout with at Least One Panel Added

Properties

General

Name

Layout

Revision

REV.001.000

☒ Default Revision

Description

Layer type

☒ Background☐ Panel☐ Sub-Panel☐ Transparent (show content only)

Orientation type

☒ Vertical☐ Horizontal

Style

CSS Classes

Inline Style

Default Header

Name

PortalDefaultHeader

Revision

APR.002.001


Version

1.0.0.1

Edit Mask...

Version host

Field	Description
Name	The name of the Layout (it cannot contain whitespace characters).
Revision	The Layout revision number (must be unique).

	The revision of the Layout which will be used in runtime. It is selected by default for a newly selected Layout (the next revisions of the Layout will not be selected as default ones).
Description	The description of the Layout.
Layer type	Defines the color scheme to be applied to some of the elements displayed in this Panel (including the Panel background). The layer corresponds to the desired visual depth for the Panel: ▶ Background – the bottommost layer of the Screen ▶ Panel – the middle layer of the Screen ▶ Sub-Panel – the topmost layer of the Screen ▶ Transparent (show content only) – there is no background, only the content is visible The same UI element can be displayed using a different color set, depending on the Panel layer on which it is being placed. 
Orientation type	The Orientation type section is available only for Layouts with Panels linked. The orientation type is important for Panels that are divided further into Sub-Panels, as the type defines the orientation of the Sub-Panels inside the parent Panel. The following types can be used: ▶ Vertical – all the child Panels of a horizontal Panel will be placed one below the other ▷ The size of a Panel is interpreted as height ▷ The width will always be adjusted automatically to fill the parent Panel ▶ Horizontal – all the child Panels of a vertical Panel will be placed one next to the other ▷ The size of a Panel is interpreted as width ▷ The height will always be adjusted automatically to fill the parent Panel ▶ Floating – not available
Style	▶ CSS Classes – apply additional CSS classes to the selected element ▶ Inline Style – apply additional CSS definitions to the selected element
Default Header	▶ Name – the name of the default Header to be displayed above the Layout (this can be overridden by the Screen configuration) ▶ Revision – the revision of the default Header; the following actions are available:

- ▷  – invokes the Views lookup, where the user can link a default header View
- ▷  – unlinks the linked header View
- ▷  – invokes the workspace of the linked header View (for details, [Header](#)) . If there is more than one revision of that View, a pop-up listing all of the revisions will appear (to open one of the revisions, double-click it).

In the case of PB Projects, the pop-up displays a default revision of the View in the current [Project](#).

Version	An auto-incremented number of a Layout. It increases when you modify and save the Layout or change its status. Click Edit Mask to enter a custom mask.
Version host	The name of the last server where a Layout has been modified and saved or its status has changed.