

Manage Steps

Add a New Step

Use one of the following options:

- ▶ Drag  (Step) from the **Toolbox** pane into the step navigation workspace or to the DFC node in the **Entity Explorer**.
- ▶ Select the DFC in the **Entity Explorer** and use the **Ins** keyboard shortcut.
- ▶ Right-click the DFC in the **Entity Explorer** and choose **Add Step** from the right-click menu.
- ▶ Choose **Add Step** from the step navigation right-click menu.

The system adds a new step to the step navigation diagram workspace with a default name, which you can modify.

Adding the first step automatically links it to the start node.

Add an Existing Step

1. Use one of the following options:

- ▶ Drag  (Existing Step) from the **Toolbox** pane into the step navigation workspace or to the DFC node in the **Entity Explorer**.
- ▶ Choose **Add Existing Step** from the step navigation right-click menu.

2. The **Add Existing Step** wizard appears. Choose a DFC from the available list:

Add Existing Step Wizard - Step 1 of 3

Reuse step
Select the DFC containing the step that you want to add.

Code / Description: Revision: Status: Subtype:

Entity name

Code	Revision	Type	Subtype
APR_DB.Load	APR.DB.001.000	DFC	Labor
APR_DB.LoadConfirmation	APR.DB.001.000	DFC	Labor
APR_DB.LoadRequiredResource	APR.DB.001.000	DFC	Generic
APR_DB.LoadRequiredSkill	APR.DB.001.000	DFC	Generic
APR_DB.LoadWCSchedule	APR.DB.001.000	DFC	Labor
APR_DB.LoadWorkspace	APR.DB.002.000	DFC	Action
APR_DB.OpenDBViewer	APR.DB.002.000	DFC	Labor
APR_DB.OpenViewer	APR.DB.001.000	DFC	Labor
APR_DB.Performance	APR.DB.001.000	DFC	Labor
APR_DB.Performance.Calculate	APR.DB.002.001	DFC	View
APR_DB.Performance.Initialize	APR.DB.002.000	DFC	Initialize
APR_DB.PreAssignment_Validate	APR.DB.001.000	DFC	Validate
APR_DB.ShowMessage	APR.DB.003.001	DFC	Labor
APR_DB.SingleWorkcenterPreAssignment_Valid...	APR.DB.001.000	DFC	Validate
APR_DB.Update	APR.DB.001.000	DFC	Labor
APR_DB.WorkSpace.Header	APR.DB.002.001	DFC	View
APR_DB.WorkSpaceClass_Router	APR.DB.002.001	DFC	Action

< Back Next > Cancel Help

3. Choose the step you would like to reuse from the available list:

Add Existing Step Wizard - Step 2 of 3

Reuse step

Select one or more steps.

Select steps to be used

Sequence No	Step	Step Description	Entity Name	Entity Re
5	Check Event Type		CAPA.PrepareNo...	APR.IMC
9	Check For New Recipients		CAPA.PrepareNo...	APR.IMC
10	Check For New Recipients		CAPA.PrepareNo...	APR.IMC
4	Check Recipients List		CAPA.PrepareNo...	APR.IMC
6	Check Recipients List		CAPA.PrepareNo...	APR.IMC
7	Compare Dates		CAPA.PrepareNo...	APR.IMC
3	Configure		CAPA.PrepareNo...	APR.IMC
11	Extension Point		CAPA.PrepareNo...	APR.IMC
1	Initialize		CAPA.PrepareNo...	APR.IMC
14	Insert History		CAPA.PrepareNo...	APR.IMC
2	Iterate		CAPA.PrepareNo...	APR.IMC
13	Prepare History		CAPA.PrepareNo...	APR.IMC
12	Send Notification		CAPA.PrepareNo...	APR.IMC

Options

☒ Copy with sub-DFCs

☐ Automatically create new revision

☐ Remember my choice

< Back Next > Cancel Help

4. Choose any of the options available in the **Options** section:

- ▶ **Copy with sub-DFCs** – an additional screen will be shown with all of the sub-DFCs linked to the selected step, from which you can select ones to copy (hold the **CTRL** key to select more than one).

Add Existing Step Wizard - Step 3 of 3

Reuse step

Verify the names and revisions of the sub-DFCs that you want to copy.

DFC Code	DFC Revision	New DFC Code	New DFC Revision	Step FUID
CAPA.CompareDates_...	APR.IMC.001.000	CAPA.CompareDates_...	APR.IMC.001.000	2b7f194f-6...

< Back Finish Cancel Help

- ▶ **Automatically create new revision** – automatically creates new revisions.
- ▶ **Remember my choice** – stores your previously selected options.

5. Click **Finish**.

Add a Step with Sub-DFC

1. Use one of the following options:

- ▶ Drag  (Step with Sub-DFC) from the **Toolbox** pane into the step navigation workspace or to the DFC node in the **Entity Explorer**.

- Choose **Add Step with Sub-DFC** from the step navigation [right-click menu](#).
2. The **Create Step with Sub-DFC** wizard appears. Choose a DFC from the available list.

Create Step With Sub-DFC Wizard - Step 1 of 2

Select the DFC.

Select DFC to be used

Code / Description: Revision: Status: Subtype:

Entity name

Code	Revision	Type	Subtype
3DMI.ProcessExplosion.Characteristic.Create.Aft...	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Characteristic.Create.Be...	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Characteristic.Link.After	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Characteristic.Link.Before	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.CheckList.Link.After	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.CheckList.Link.Before	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.DataCollectPlan.Create...	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.DataCollectPlan.Create...	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Notice.Create.After	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Notice.Create.Before	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Notice.Link.After	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Notice.Link.Before	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Signature.Create.After	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.Signature.Create.Before	APR.3DX.22.1	DFC	Interfac
3DMI.ProcessExplosion.WipOperation.Create.Aft...	APR.3DX.22.1	DFC	Interfac

☐ Create copy before linking

< Back Finish Cancel Help

3. To create a copy of a DFC, select the **Create copy before linking** check box. Click **Next**, and enter a name and revision for the copy.
4. Click **Finish**.

Changes to the diagram include:

- A step with the same name as the DFC is added to the diagram.
- A function of type Sub-DFC is created within the new step, which is configured to call the selected DFC.
- The function inputs and outputs are configured as session variables. The names of source session variables names are the same as the DFC external inputs.
- No incoming or outgoing arrows are created to or from the step.

Select a Step

Select a Single Step

Use one of the following options:

- Click on the step in the step navigation workspace .
- Draw a box around the step in the step navigation workspace.
- Select the step in the **Entity Explorer**.

The **Background Tasks** and **Properties** tool panes are populated with information regarding the selected step. The system also highlights all of the step's incoming and outgoing connections in green.

Select a Group of Steps

Use one of the following options:

- ▶ Draw a box around the steps in the step navigation workspace.
- ▶ In **Entity Explorer** or the step navigation workspace, click on each step while holding the **CTRL** key.

The system highlights in green all of the incoming and outgoing connections for each of the selected steps.

Selected steps can be grouped. For more information, see [Group or Ungroup Steps](#).

Duplicate a Step

In the step navigation diagram workspace:

1. [Select one or more steps](#) you want to duplicate.
2. Use one of the following options:
 - ▶ The **CTRL+D** [keyboard shortcut](#).
 - ▶ Choose **Duplicate Selection** from the step navigation [right-click menu](#) or the **Edit** main menu.
 - ▶ Use the **CTRL+C** and **CTRL+V** [keyboard shortcuts](#).
 - ▶ Choose **Copy** and **Paste** from the **Edit** menu.
 - ▶ Click  (Copy) and  (Paste) in the [toolbar](#).
 - ▶ Choose **Copy** and **Paste** from the **Entity Explorer** [right-click menu](#).

In **Entity Explorer**:

1. [Select one or more steps](#) you want to duplicate.
2. Use one of the following options:
 - ▶ The **CTRL+C** and **CTRL+V** [keyboard shortcuts](#).
 - ▶ Choose **Copy** and **Paste** from the **Edit** menu.
 - ▶ Click  (Copy) and  (Paste) in the [toolbar](#).
 - ▶ Choose **Copy** and **Paste** from the **Entity Explorer** [right-click menu](#).
3. Paste steps into the same or different DFC.

The system creates copies of the steps with their original names and contents. Incoming and outgoing arrows for the new steps are created unless they go to steps that are outside of the selection.

Move a Step

1. [Select the step or group of steps](#) you want to move.
2. Drag the steps and drop them anywhere in the step navigation diagram workspace.

Copy a Diagram Element

1. Select one or more diagram element elements that you want to copy.
2. Use one of the following options:
 - ▶ The **CTRL+C** and **CTRL+V** [keyboard shortcuts](#).
 - ▶ Choose **Copy** and **Paste** from the **Edit** menu.
 - ▶ Click  (Copy) and  (Paste) in the [toolbar](#).
 - ▶ Choose **Copy** and **Paste** from the **Entity Explorer** [right-click menu](#).

A diagram or its elements can be pasted:

- ▶ Back into Process Builder into the same or different DFC.
- ▶ As an image into an application like Microsoft Word or Visio.

Edit a Step Name

1. Select the step you want to rename.
2. Use one of the following options:
 - ▶ Use the **F2** keyboard shortcut.
 - ▶ Choose **Rename** from the **Entity Explorer** right-click menu or the **Edit** menu.
 - ▶ Click the name part of the step in the step navigation diagram.
 - ▶ Select the **Name** field on the **General** tab of the step's **Properties** tool pane.
3. Enter a new name.
4. Click **ENTER** to confirm.

Add or Edit a a Step Description

1. Select the step for which you want to edit the description.
2. Select the **Description** field on the **General** tab of the step's **Properties** tool pane.
3. Enter a description.
4. Click **ENTER** to confirm.

Add or Edit a Step Description Using the Navigation Diagram

1. Use one of the following options:
 - ▶ Click the  icon on the information bar of the step box.
 - ▶ Select the step and use the **SHIFT+F2** keyboard shortcut.
 - ▶ Choose **Edit Description** from the step navigation right-click menu or the **Navigation** menu.
 - ▶ Choose **Show/Hide Step Description** from the step navigation right-click menu or the **Navigation** menu, and click the description box to make it editable.
2. Add a description. Click anywhere outside of the description box to exit edit mode.

Select the pin in the corner of the description box to keep the box permanently visible.

Remove a Step

1. In **Entity Explorer** or step navigation diagram, select one or more steps.
2. Use one of the following options:
 - ▶ The **DEL** keyboard shortcut.
 - ▶ Choose **Delete** from the:
 - ▶ **Edit** menu.
 - ▶ **Entity Explorer** right-click menu.
 - ▶ Step navigation right-click menu.

The system removes the steps from diagram. Incoming and outgoing arrows for these steps are removed as well.