


Panel Properties

The Panel **Properties** pane differs depending on the Panel's configuration. There are two different cases:

Panel without Any Sub-Panels

Entity Explorer View



General Tab Properties Pane

Properties

General

Name
SUB-PANEL

Layer type
☐ Background ☒ Panel ☐ Sub-Panel
☐ Transparent (show content only)


Height
☒ Fill ☐ Specific 0 Percent ☐ Match Content

Style
CSS Classes
Inline Style

Default View
Name
PortalGrid
Revision
APR.TPL.001.000

Panel with at Least One Sub-Panel

Entity Explorer View



General Tab Properties Pane

Properties

General

Name
SUB-PANEL

Layer type
☐ Background ☒ Panel ☐ Sub-Panel
☐ Transparent (show content only)

Orientation type
☒ Vertical ☐ Horizontal

Height
☒ Fill ☐ Specific 0 Percent ☐ Match Content

Style
CSS Classes
Inline Style

Field	Description				
Name	The name of the Panel (it cannot contain whitespace characters).				
Layer type	Defines the color scheme to be applied to some of the elements displayed in this Panel (including the Panel background). The layer corresponds to the desired visual depth for the Panel: ▶ Background – the bottommost layer of the Screen ▶ Panel – the middle layer of the Screen ▶ Sub-Panel – the topmost layer of the Screen ▶ Transparent (show content only) – there is no background, only the content is visible The same UI element can be displayed using a different color set, depending on the Panel layer on which it is being placed. <table><tr><td>PANEL</td><td>SUB-PANEL</td><td>TRANSPARENT</td><td>BACKGROUND</td></tr></table>	PANEL	SUB-PANEL	TRANSPARENT	BACKGROUND
PANEL	SUB-PANEL	TRANSPARENT	BACKGROUND		

Orientation type	This section is available only for Panels that have Sub-Panels. The type is important for Panels that are divided further into Sub-Panels, as the type defines the orientation of the Sub-Panels inside the parent Panel. The following types can be used: ▶ Vertical – all the child Panels of a horizontal panel will be placed one below the other ▷ The size of a Panel is interpreted as height ▷ The width will always be adjusted automatically to fill the parent Panel ▶ Horizontal – all the child Panels of a horizontal panel will be placed one next to the other ▷ The size of a Panel is interpreted as width ▷ The height will always be adjusted automatically to fill the parent Panel
Height/Width	The size of the Panel represents its width or height, depending on the parent Panel type: ▶ If the parent Panel type is horizontal, the size of its child Panels is interpreted as its height ▷ The width will always be adjusted automatically to fill the parent Panel ▶ If the parent Panel type is vertical, the size of its child Panels is interpreted as its width ▷ The height is adjusted to the parent Panel There are three options to define the height or width of the Panel: ▶ Fill – takes available space. When the total Layout size is greater than the window size, it may decrease to 0 pixels. ▶ Specific – the size can be defined in pixels or percentage ▶ Match Content – uses only as much space as it is needed by its child content Keep in mind that the Match Content option does not define the extrinsic size for the View container so using percentage dimensions in the View content (e.g., <code>style="height: 100%;"</code>) may not work as intended. Screen Flows Layouts are based on the CSS Flexbox. Some Layout configurations might not work as expected. You cannot mix size measures (pixels and percentages) in child Panels of the same parent Panel.
Style	▶ CSS Classes – apply additional CSS classes to the selected element

► **Inline Style** – apply additional CSS definitions to the selected element

Default View

This section is only available for Panels that have no Sub-Panels.

A Default View is a way to share a particular View DFC between multiple Screens. It will be suppressed by a View mapped to a Panel in a Screen definition. If you want a View to be shared across more than one Screen, you can link it directly on a Layout Panel as a Default View.

- **Name** – the name of the default View to be displayed in this Panel on any Screen that uses the Layout (this can be overridden by the Screen configuration)
- **Revision** – the revision of the default View; the following actions are available:
 - ▷  – invokes the **Views** lookup, where the user can copy and link a Default View (this option is not available for Layouts which are part of a [Project](#))
 - ▷  – invokes the **Views** lookup, where the user can link a Default View
 - ▷  – unlinks the linked View
 - ▷  – invokes the workspace of the linked View.
 - ▷ If there is more than one revision of that View, a pop-up listing all of the revisions will appear (to open one of the revisions, double-click it).

In the case of PB Projects, the pop-up displays a default revision of the View in the current [Project](#).