

View: General Tab

Properties

General

Advanced

Name

View

Revision

REV.001.000

Subtype

General

☒ Default Revision

Title

Code:

+

Translation:

Description

View DFC

Name

EquipmentMaintenance.Alert.CreateAlert.List_View

Revision

APR.MNC.002.002

Version

1.0.0.1

Edit Mask...

Version host

Field	Description
Name	The name of the View.
Revision	The unique View revision number.
Default Revision	If selected, this revision of the View will be used in runtime. A newly created View entity is set automatically as the default revision. The next revisions will not become "default" automatically.
Title	▶ Code – the name of the Dictionary Item of the View title; the following actions are available: ▶ + – adds the Dictionary Item (written in the text box) to the dictionary and links it to the View title ▶ – invokes the Dictionary Items suggestion lookup window, which lists the existing Dictionary Items from which the user may choose ▶ When the user enters a part of the Dictionary Item name, the system suggests a list of matching entries from the database ▶ The chosen Dictionary Item is linked to the View title

	▷  – unlinks a previously added Dictionary Item (it is removed from the Code field) ▷  – opens the Dictionary Translations screen in the context of linked Dictionary Items (for more information, refer to the Dictionary Translations topic in the Dictionary Help) ▶ Translation – the translation of the View's title according to the translation added in the Dictionary Translations screen A value of a variable from the Screen Flows session can be displayed in a pop-up title. In order to do this, specify a variable name in curly brackets, e.g., "Edit WIP Order: {WIPOrderNo}".
Description	The description of a View.
Subtype	The type of a View. There are five options: ▶ HTML – a special type reserved for offline mode ▶ HTML Header – a special type reserved for Views which may be linked as the Header on an Offline Screen ▶ General – a standard View (without Forms) ▶ Form – a View with the possibility to add Forms ▶ Header – a special type reserved only for Views which may be linked as a Header on the Screen
View DFC	The section appears only for Views of type General, Form and Header. ▶ Name – the name of the View DFC linked to the View ▶ Revision – the revision of the View DFC; the following actions are available: ▷  – invokes the DFCs lookup window, where the user can copy and link a View DFC ▷  – invokes the DFCs lookup window, where the user can link a View DFC ▷  – unlinks the linked DFC ▷  – invokes the workspace of the linked DFC. If there is more than one revision of that DFC, a pop-up listing all of the revisions will appear (to open one of the revisions, double-click it). In the case of PB Projects, the pop-up will display default revision of the DFC (of the View type) in the current Project.
Version	An auto-incremented number of a View. It increases when you modify and save the View or change its status. Click Edit Mask to enter a custom mask.
Version host	The name of the last server where a View has been modified and saved or its status has changed.