```
.widget-area-sidebar improdisa
    .widget-area-sidebar teathrand
347
348
       font-size: 13px;
349
352
   /* ≃Menu
   *access {
     display: inline-block;
     height: 69px;
     float: right;
     margin: 11px 28px 0px 0px;
     max-width: 800px;
  ARCERSS UL {
    funt-size: 13px;
    Hist-style: none;
    margin: 0 0
  Comando LOOP
      AT no ABAP
         left block;
  DEDL
800
800
F4
          11. FE
```



## Comando LOOP AT

O comando LOOP AT é um loop de tabelas internas no ABAP.

Desenvolvedores ABAP podem criar um programa listando pedidos de compras de um intervalo de um mês.

O comando LOOP serve para ler registro a registro do Pedido de Compras gravados na tabela interna.

## Sintaxe:

**LOOP AT** <tabela interna> [**INTO** <work-área>]

[FROM <índice 1ª linha>] [TO <índice ultima linha>] [WHERE <expressão lógica>]

```
REPORT Z AEREO 1.
tables: scarr.
Data w_aereo type scarr. "workarea
Data t_aereo type TABLE OF scarr. "tabela interna
Data moeda TYPE c LENGTH 3.
" tabela interna lê as informações da tabela SCARR
" workarea vai imprimir em tela as informações obtidas da tabela
interna t aereo
"w aereo-mandt = '001'.
w_aereo-carrid = '2022'.
"w aereo-carrname = 'LATAM'.
"w aereo-currcode = 'BRZ'.
"Entrada de dados
SELECTION-SCREEN BEGIN OF BLOCK blocol WITH FRAME TITLE TEXT-001.
    Parameters: p_carrid like w_aereo-carrid,
               p_carrnm like w_aereo-carrname.
  "PARAMETER: p_carrid type scarr-carrid ,
            p carrnm type scarr-carrname.
 SELECTION-SCREEN END OF BLOCK blocol.
 Select mandt,
       carrid,
       carrname,
       currcode
into TABLE @t_aereo
  FROM scarr
 WHERE carrid = @p_carrid or carrname = @p_carrnm.
If sy-subrc = 0.
 loop at t_aereo into w_aereo.
   Write: / 'ID: '
                              , w_aereo-carrid.
   Write: / 'Cia Aerea: '
                              , w_aereo-carrname.
   Write: / 'Código da moeda: ' , w aereo-currcode.
 endloop.
EndIf.
```