HO CHI MINH CITY UNIVERSITY OF TECHNOLOGY FACULTY OF COMPUTER SCIENCE AND ENGINEERING



COMPUTER NETWORK

Wireshark Lab 09


Lecturer: Nguyen Le Duy Lai Author: Vuong Le Huy

June, 2020

Contents

1	What is the 48-bit Ethernet address of your computer?	3
2	What is the 48-bit destination address in the Ethernet frame? Is this the Ethernet address of gaia.cs.umass.edu? (Hint: the answer is no). What device has this as its Ethernet address?	4
3	Give the hexadecimal value for the two-byte Frame type field. What upper layer protocol does this correspond to?	4
4	How many bytes from the very start of the Ethernet frame does the ASCII "G" in "GET" appear in the Ethernet frame?	5
5	What is the value of the Ethernet source address? Is this the address of your computer, or of gaia.cs.umass.edu (Hint: the answer is no). What device has this as its Ethernet address?	6
6	What is the destination address in the Ethernet frame? Is this the Ethernet address of your computer?	6
7	Give the hexadecimal value for the two-byte Frame type field. What do the $\mathrm{bit}(s)$ whose value is 1 mean within the flag field?	6
8	ow many bytes from the very start of the Ethernet frame does the ASCII "O" in "OK" (i.e.,the HTTP response code) appear in the Ethernet frame?	6
9	Write down the contents of your computer's ARP cache. What is the meaning of each column value?	7
10	What are the hexadecimal values for the source and destination addresses in the Ethernet frame containing the ARP request message?	7
11	Give the hexadecimal value for the two-byte Ethernet Frame type field. What do the bit(s) whose value is 1 mean within the flag field?	8
12	Download the ARP specification from ftp://ftp.rfc-editor.org/innotes/std/std37.txt. A readable, detailed discussion of ARP is also at http://www.erg.abdn.ac.uk/users/gorry/course /inet-pages/arp.html. 12.1 How many bytes from the very beginning of the Ethernet frame does the ARP opcode field begin? The ARP opcode field begins 20 bytes from the very beginning	8
	of the Ethernet frame	9 9 9

13 Now find the ARP reply that was sent in response to the ARP request. 13.1 How many bytes from the very beginning of the Ethernet frame does the ARP	9
opcode field begin?	. 9
13.2 What is the value of the opcode field within the ARP-payload part of the Ethernet frame in which an ARP response is made?	. 9
13.3 Where in the ARP message does the "answer" to the earlier ARP request appear—the IP address of the machine having the Ethernet address whose corresponding	
IP address is being queried?	•
14 What are the hexadecimal values for the source and destination addresses	in
the Ethernet frame containing the ARP reply message?	9
15 Open the ethernet-ethereal-trace-1 trace file in	
http://gaia.cs.umass.edu/wireshark-labs	
/wireshark-traces.zip.	
The first and second ARP packets in this trace correspond to an ARP reque	
sent by the computer running Wireshark, and the ARP reply sent to the con-	
puter running Wireshark by the computer with the ARP-requested Ethern	
address. But there is yet another computer on this network, as indicated	•
packet 6 another ARP request. Why is there no ARP reply (sent in respont to the ARP request in packet 6) in the packet tracer?	ıse 10
to the Arti request in packet of in the packet tracer:	10



1 What is the 48-bit Ethernet address of your computer?

The Ethernet address of my computer is 00:09:5b:61:8e:6d.


What is the 48-bit destination address in the Ethernet frame? Is this the Ethernet address of gaia.cs.umass.edu? (Hint: the answer is no). What device has this as its Ethernet address?

The destination address 00:0c:41:45:90:a8 is not the Ethernet address of gaia.cs.umass.edu. It is the address of my Linksys router, which is the link used to get off the subnet. not.

3 Give the hexadecimal value for the two-byte Frame type field. What upper layer protocol does this correspond to?

The hex value for the Frame type field is 0x0800. This corresponds to the IP protocol (the frame type filed indicates that the nest layer above IP –the layer to which the payload of the Ethernet frame will be passed –is IP.

4 How many bytes from the very start of the Ethernet frame does the ASCII "G" in "GET" appear in the Ethernet frame?



The ASCII "G" appears 52 bytes from the start of the Ethernet frame. There are 14 B Ethernet frame, and then 20 bytes of IP header followed by 20 bytes of TCP header before the HTTP data is encountered.

What is the value of the Ethernet source address? Is this the address of your computer, or of gaia.cs.umass.edu (Hint: the answer is no). What device has this as its Ethernet address?

The source address 00:0c:41:45:90:a8 is neither the Ethernet address of gaia.cs.umass.edu nor the address of my computer. It is the address of my Linksys router, which is the link used to get onto my subnet.


6 What is the destination address in the Ethernet frame? Is this the Ethernet address of your computer?

The destination address 00:09:5b:61:8e:6d is the address of my computer.

7 Give the hexadecimal value for the two-byte Frame type field. What do the bit(s) whose value is 1 mean within the flag field?


The hex value for the Frame type field is 0x0800. This value corresponds to the IP protocol (see also answer to 3. above).

8 ow many bytes from the very start of the Ethernet frame does the ASCII "O" in "OK" (i.e.,the HTTP response code) appear in the Ethernet frame?



The ASCII "O" appears 52 bytes from the start of the Ethernet frame. Again, there are 14 bytes of Ethernet frame, and then 20 bytes of IP header followed by 20 bytes of TCP header before the HTTP data is encountered.

9 Write down the contents of your computer's ARP cache. What is the meaning of each column value?



The Internet Address column contains the IP address, the Physical Address column contains the MAC address, and the type indicates the protocol type.


What are the hexadecimal values for the source and destination addresses in the Ethernet frame containing the ARP request message?

The hex value for the source address is 00:d0:59:a9:3d:68. The hex value for the destination address is ff:ff:ff:ff:ff;ff;ff, the broadcast address.

Give the hexadecimal value for the two-byte Ethernet Frame type field. What do the bit(s) whose value is 1 mean within the flag field?

The hex value for the Ethernet Frame type field is 0x0806, for ARP.

Download the ARP specification from ftp://ftp.rfc-editor.org/innotes/std/std37.txt. A readable, detailed discussion of ARP is also at http://www.erg.abdn.ac.uk/users/gorry/course/inet-pages/arp.html.



12.1 How many bytes from the very beginning of the Ethernet frame does the ARP opcode field begin? The ARP opcode field begins 20 bytes from the very beginning of the Ethernet frame.

The ARP opcode field begins 20 bytes from the very beginning of the Ethernet frame.

12.2 What is the value of the opcode field within the ARP-payload part of the Ethernet frame in which an ARP request is made?

The hex value for opcode field withing the ARP-payload of the request is 0x0001, for request.

12.3 Does the ARP message contain the IP address of the sender?

Yes, the ARP message containing the IP address 192.168.1.105 for the sender.

12.4 Where in the ARP request does the "question" appear –the Ethernet address of the machine whose corresponding IP address is being queried?

The field "Target MAC address" is set to 00:00:00:00:00:00 to question the machine whose corresponding IP address (192.168.1.1) is being queried.

- 13 Now find the ARP reply that was sent in response to the ARP request.
- 13.1 How many bytes from the very beginning of the Ethernet frame does the ARP opcode field begin?

The ARP opcode field begins 20 bytes from the very beginning of the Ethernet frame.

13.2 What is the value of the opcode field within the ARP-payload part of the Ethernet frame in which an ARP response is made?

The hex value for opcode field withing the ARP-payload of the request is 0x0002, for reply.

13.3 Where in the ARP message does the "answer" to the earlier ARP request appear —the IP address of the machine having the Ethernet address whose corresponding IP address is being queried?

The answer to the earlier ARP request appears in the "Sender MAC address" field, which contains the Ethernet address 00:06:25:da:af:73 for the sender with IP address 192.168.1.1.

What are the hexadecimal values for the source and destination addresses in the Ethernet frame containing the ARP reply message?

The hex value for the source address is 00:06:25:da:af:73 and for the destination is 00:d0:59:a9:3d:68.

Open the ethernet-ethereal-trace-1 trace file in http://gaia.cs.umass.edu/wireshark-labs/wireshark-traces.zip.

The first and second ARP packets in this trace correspond to an ARP request sent by the computer running Wireshark, and the ARP reply sent to the computer running Wireshark by the computer with the ARP-requested Ethernet address. But there is yet another computer on this network, as indicated by packet 6 another ARP request. Why is there no ARP reply (sent in response to the ARP request in packet 6) in the packet tracer?

There is no reply in this trace, because we are not at the machine that sent there quest. The ARP request is broadcast, but the ARP reply is sent back directly to the sender's Ethernet address.