

BOSEONG GREEN TEA

User Manual

A focused richness processor that turns thin, spiky sources into smoother, denser, creamier sound.



Richness with a quieter edge

Build body and sustain without losing the source's identity.

Boseong Green Tea turns thin or spiky material toward a smoother, denser, creamier presentation. Grow makes the complete richness move, combining transient rounding, generated density, sustain, low-mid body, and a slightly more settled placement. Body, Focus, and Air let you shape that character for the source.

COMPATIBILITY

MACOS

AU / VST3 / AAX

Current plug-in formats

WINDOWS

VST3 / AAX

Current plug-in formats

AUDIO

Mono / Stereo

Matching input and output

Product version 1.0.0. Format availability follows the current release.

FIRST SOUND

- 1 Start with the default setting and play a representative section.
- 2 Raise or lower Grow until the source reaches the right richness.
- 3 Shape Body, set Focus, then open the result with Air.
- 4 Match Output. Add AUTO only if stronger Grow feels quieter.



CURRENT INTERFACE

The plug-in opens at a fixed 500 x 500 layout. Drag vertically on a knob. Double-click a knob value to enter an exact percentage or dB value.

Interface overview

Every visible control, mapped to the current production UI.



- | | | | |
|------------------------|--------------------------|------------------------|-----------------------|
| 1 Preset | 11 character starts | 5 Air | Silky to open top |
| 2 Grow | Complete richness macro | 6 Output | Final manual level |
| 3 Body | Light to deep mass | 7 AUTO | Optional level assist |
| 4 Focus | Loose to tight placement | | |

One move for richness, three for character

Grow sets the transformation. Body, Focus, and Air decide how it belongs to the source.

MAIN MACRO

Grow

Thin / Spiky -> Rich / Creamy

Grow coordinates the full character: attacks become rounder, density and low-mid body are generated, sustain feels creamier, and the source can settle slightly farther back.

SUBTLE

Low values

MUSICAL

Core range

EXTREME

Above about 70

CHARACTER

Body

LIGHT <-> DEEP

Adds low-mid body and nonlinear mass. Stop when the source feels grounded, before it feels crowded.

CHARACTER

Focus

LOOSE <-> TIGHT

Places the generated sustain and density more broadly or more tightly around the source.

CHARACTER

Air

SILKY <-> OPEN

Adjusts openness and top character after the creamy center has been formed.

PRACTICAL CUE

If the source still feels sharp

Raise Grow before chasing individual controls.

If it becomes heavy

Reduce Body or Grow; high Body is not a universal goal.

If it feels too covered

Open Air, then re-check Output at matched level.

Judge the character at matched loudness. AUTO can help with stronger Grow settings, but it remains optional and separate from the tone controls.

Shape the result by ear

All host-visible controls are listed with practical listening cues.

CONTROL	SHAPES	LISTEN FOR
Grow 0-100% default 50%	The complete richness movement: rounding, density, sustain, body, and placement.	Raise it until the source feels fuller and less spiky. The upper range becomes darker, stronger, and deliberately more extreme.
Body 0-100% default 45%	Low-mid body and nonlinear mass inside the generated richness.	Move from LIGHT toward DEEP until the source gains weight. Dense or bass-heavy material may need less.
Focus 0-100% default 55%	How the generated sustain and density settle around the source.	LOOSE feels broader and softer. TIGHT keeps the added character more gathered around the source.
Air 0-100% default 60%	Openness and top character after the creamy processing.	Move from SILKY toward OPEN to restore edge and light without undoing the richer center.
Output -12 to +12 dB default 0 dB	Final manual level trim after processing and optional AUTO assistance.	Match the processed level to the track by ear and leave enough headroom for peaks.
AUTO Off / On default Off	Optional Grow-dependent level assistance for stronger richness settings.	Use it when higher Grow feels quieter. It does not move Output and it is not a limiter or peak protector.

HEADROOM NOTE

AUTO is level assistance, not limiting or clipping prevention. Hot input and positive Output can exceed available headroom, so check peaks in your DAW.

Start from a real preset

Use these as character starts, then match the setting to the actual source.

Harsh / Thin Vocal

START: VOCAL VELVET

G46 B34 F64 A70

Rounds spiky edges while keeping enough openness around the vocal.

Clean / DI Guitar

START: GUITAR CREAM

G44 B50 F60 A62

Adds body and creamy sustain without assuming the guitar needs an extreme setting.

Synth Lead

START: SOFT SYNTH

G52 B42 F56 A62

Settles a digital edge and builds a denser, smoother center.

Snare / One-shot

START: GENTLE INFUSION

G28 B36 F58 A66

A restrained start for rounding the hit while preserving useful definition.

Thin Pluck

START: MATCHA CREAM

G56 B52 F50 A56

Turns a narrow pluck into a fuller gesture with more body and tail.

Bass

START: BASS SILK

G40 B58 F68 A54

Use moderately; compare the fundamental and reduce Body if weight becomes crowded.

Drum Loop

START: SMOOTH BUS

G34 B40 F66 A66

A moderate bus start for softer peaks and a more connected texture.

SIMPLE FLOW

01

Set Grow

02

Shape Body

03

Set Focus

04

Open with Air

05

Match Output

Factory presets

Presets change Grow, Body, Focus, and Air. Output and AUTO stay where you left them.

PRESET	GROW	BODY	FOCUS	AIR
Default	50%	45%	55%	60%
Gentle Infusion	28%	36%	58%	66%
Matcha Cream	56%	52%	50%	56%
Deep Cream	62%	70%	58%	50%
Vocal Velvet	46%	34%	64%	70%
Soft Synth	52%	42%	56%	62%
Bass Silk	40%	58%	68%	54%
Guitar Cream	44%	50%	60%	62%
Smooth Bus	34%	40%	66%	66%
Full Matcha	72%	58%	54%	56%
Extra Thick	86%	66%	58%	52%

PROJECT RECALL

Your DAW saves all six parameters and the selected preset name. Reopening the project restores the last actual values and refreshes the interface.

MANUAL EDITS

After choosing a preset, refine any knob by hand. The preset name remains visible while your edited parameter values are saved with the project.

PRESET WORKFLOW

Choose a preset for a useful character direction, then adjust Grow and the three character controls for the source. Switching presets changes only those four controls. Output and AUTO remain independent session choices.

Support and legal

SUPPORT

support@farmverb.com

farmverb.com

When contacting support, include the product version, platform, plug-in format, host name, and a short description of the issue.

END USER LICENSE AGREEMENT

Use of Boseong Green Tea is governed by the FarmVerb Software End User License Agreement. Read the current agreement at:

farmverb.com/eula

LICENSE AND ACTIVATION

This edition does not describe an activation workflow. Follow only the current materials supplied with your licensed build or instructions provided by FarmVerb support.

