DEPARTMENT OF ELECTRONICS AND COMMUNICATION ENGINEERING IBM NALAIYA THIRAN PROJECT

Preparation Phase

Date	20 September 2022
Team ID	PNT2022TMID03479
Project Name	IoT Based Smart Crop Protection System for Agriculture
Maximum Marks	2 Marks

Assignment 1:

Publish sensor parameters like Temperature, Humidity, and Soil Moisture to the IBM IoT platform. Solution:

#include <LiquidCrystal.h> LiquidCrystal lcd(8,9,10,11,12,13);//rs,en,data pins d4 -d7 float TEMP; int MOISURE, HUM; const int buzzer=6; const int motor=7; int led=4,temp=0,i=0; char str[30]; int aa=0, dt=0////temp; int dh=0;///hum int s1=0.s3=0: void setup() { lcd.begin(16,2);Serial.begin(9600); pinMode(buzzer, OUTPUT); pinMode(motor, OUTPUT); digitalWrite(buzzer, LOW); digitalWrite(motor, LOW); lcd.clear(); lcd.setCursor(0,0);lcd.print("IOT Based "); lcd.setCursor(0,1);lcd.print("Agriculture Crop"); delay(5000);lcd.clear(); lcd.setCursor(0,0);lcd.print("Field Monitoring"); lcd.setCursor(0,1);lcd.print("Irrigation"); delay(5000);lcd.clear(); lcd.setCursor(0,0);lcd.print(" Automation"); lcd.setCursor(0,1);lcd.print("using GPRS ");

```
delay(5000);lcd.clear();
gsm_init();lcd.clear();
digitalWrite(buzzer, LOW);
digitalWrite(motor, LOW);
void loop() {
aa=aa+1;
digitalWrite(buzzer, LOW);
lcd.clear();
TEMP = analogRead(0);
TEMP=(TEMP*500)/1023;
lcd.setCursor(0,0);lcd.print("T:");lcd.setCursor(3,0);lcd.print(TEMP);delay(200);if(TEMP<50){dt=0;delay(100);}
if(TEMP>50){
dt=dt+1;
if(dt==2)
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);lcd.clear();send_gprs();delay(500);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
lcd.clear();lcd.setCursor(0,0);lcd.print("SENDING SMS");lcd.setCursor(0,1);lcd.print("TEMP ALERT");
Serial.println("AT+CMGF=1");delay(400);
Serial.println("AT+CMGS=\"9148300815\"");delay(400);
Serial.println("Over Temperature\n");delay(100);
Serial.print("Temp=");delay(100);Serial.print(TEMP);delay(500);Serial.write(26);delay(500);
Serial.print("AT\r\n");delay(1000);Serial.print("AT\r\n");delay(1000);Serial.println("AT+CMGF=1");delay(1000);
}}
HUM= analogRead(1);HUM =HUM/2;
HUM=HUM+12;
lcd.setCursor(0,1);lcd.print("H:");lcd.setCursor(3,1);lcd.print(HUM);delay(2500);if(HUM<30){dh=0;delay(100);}
if(HUM>45){
dh=dh+1;
if(dh==2){
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);lcd.clear();send_gprs();delay(500);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
lcd.clear();lcd.setCursor(0,0);lcd.print("SENDING SMS");lcd.setCursor(0,1);lcd.print("HUMIDITY ALERT");
Serial.println("AT+CMGF=1");delay(400);
Serial.println("AT+CMGS=\"9148300815\"");delay(400);
Serial.println("HUMIDITY ALERT\n");delay(100);
Serial.print("HUM=");delay(100);Serial.print(HUM);delay(500);Serial.write(26);delay(500);
Serial.print("AT\r\n"); delay (1000); Serial.print("AT\r\n"); delay (1000); Serial.println("AT+CMGF=1"); delay (1000); Serial.println("AT+CMGF=1"); delay (1000); delay (1000); Serial.println("AT+CMGF=1"); delay (1000); delay
}}
MOISURE = analogRead(2); MOISURE= MOISURE/4; MOISURE=256-MOISURE;
lcd.setCursor(9,0);
```

```
lcd.print("M: ");
lcd.setCursor(11,0);
lcd.print(MOISURE);
delay(500);
if(MOISURE<100){
s1=s1+1;
if(s1==5){
s3=0;
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);lcd.clear();send_gprs();delay(500);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
lcd.clear();lcd.setCursor(0,0);lcd.print("SENDING SMS");delay(2000);
lcd.clear();
lcd.setCursor(0,0);lcd.print("FEILD AT DRY");
lcd.setCursor(0,1);lcd.print("MOTOR ON");delay(2000);
digitalWrite(motor, HIGH);
Serial.print("AT\r\n");delay(2000);Serial.print("AT\r\n");delay(2000);
Serial.println("AT+CMGF=1");delay(400);Serial.println("AT+CMGS=\"9148300815\"");delay(400); // use your 10 digit cell no. here
Serial.println("FEILD AT DRY\n");delay(100);
Serial.println("MOTOR ON\n");delay(100);
Serial.write(26);delay(100);
Serial.print("AT\r\n");delay(1000);Serial.print("AT\r\n");delay(1000);Serial.println("AT+CMGF=1");delay(1000);
motor_gprs();
delay(2000);
pump_gprs();
delay(2000);
delay(100);
if(MOISURE>200){
s3=s3+1;
if(s3==5){
s1=0;
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);lcd.clear();send_gprs();delay(500);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
lcd.clear();lcd.setCursor(0,0);lcd.print("SENDING SMS");delay(2000);
lcd.clear();
lcd.setCursor(0,0);lcd.print("FEILD AT WET");
lcd.setCursor(0,1);lcd.print("MOTOR OFF");delay(2000);digitalWrite(motor, LOW);
Serial.print("AT\r\n"); delay(2000); Serial.print("AT\r\n"); delay(2000);
Serial.println("AT+CMGF=1");delay(400);Serial.println("AT+CMGS=\"9148300815\"");delay(400); // use your 10 digit cell no. here
Serial.println("FEILD AT WET\n");delay(100);
```

```
Serial.println("MOTOR OFF\n");delay(100);
Serial.write(26);delay(100);
Serial.print("AT\r\n");delay(1000);Serial.print("AT\r\n");delay(1000);Serial.println("AT+CMGF=1");delay(1000);
motor_gprs();
delay(2000);
pump_gprs();
delay(2000);
delay(100);
if(aa==10){
lcd.clear();
send_gprs();
delay(2000);
pump_gprs();
delay(2000);
aa=0;
}}
void motor_gprs(){
lcd.clear();lcd.print("GPRS SENDING");
boolean test47_flag=1;
while(test47_flag){Serial.print("AT+HTTPPARA=\"URL\\",\"http://iotbabycare.com/iot_green_agrimnr/put_motor.php?mot=motor");
Serial.print("\"");Serial.print("\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test47_flag=0;}delay(1000);}
lcd.clear();lcd.print("SENT COMPLETED");delay(10000);lcd.clear()
lcd.clear();lcd.print("ACTION");
boolean\ test 48\_flag=1; while (test 48\_flag) \{Serial.print ("AT+HTTPACTION=0 \ | \ n"); \}
while(Serial.available()>0){if(Serial.find("OK"))test48_flag=0;}delay(1000);}
lcd.clear();lcd.print("SEND OK");delay(2000); delay(2000);delay(2000);
boolean at_flagd=1; while(at_flagd) {Serial.println("AT"); while(Serial.available()>0) {if(Serial.find("OK"))at_flagd=0;} delay(1000);}
}
void send_gprs(){
lcd.clear();lcd.print("GPRS SENDING");
boolean test7_flag=1;
while(test7_flag){Serial.print("AT+HTTPPARA=\"URL\",\"http://iotbabycare.com/iot_green_agrimnr/put_data.php");
Serial.print("?temp=");Serial.print(TEMP);
Serial.print("&hum=");Serial.print(HUM);
Serial.print("&mos=");Serial.print(MOISURE);
Serial.print("\""); Serial.print("\r\n");
while (Serial.available ()>0) \{ if (Serial.find ("OK")) test7\_flag=0; \} delay (1000); \}
lcd.clear();lcd.print("SENT COMPLETED");delay(10000);lcd.clear();
lcd.clear();lcd.print("ACTION");
boolean\ test8\_flag=1; while (test8\_flag) \{Serial.print("AT+HTTPACTION=0 \ | \ n''); \}
```

```
while (Serial.available ()>0) \{ if (Serial.find ("OK")) test8\_flag=0; \} delay (1000); \}
lcd.clear();lcd.print("SEND OK");delay(2000); delay(2000);delay(2000);
void pump_gprs(){
boolean at_flagd=1; while(at_flagd) {Serial.println("AT"); while(Serial.available()>0) {if(Serial.find("OK"))at_flagd=0;} delay(1000);}
lcd.clear();lcd.print("PING TO WEBSITE");
test17_flag=1; while(test17_flag){Serial.print("AT+HTTPPARA=\"URL\",\"http://iotbabycare.com/iot_green_agrimnr/get_data.php"); Serial.prin
t("\");Serial.print("\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test17_flag=0;}delay(1000);}
lcd.clear();lcd.print("WEBLINK SUCESS");delay(1000);
lcd.clear();lcd.print("HTTP ACTION");
boolean\ test18\_flag=1; while (test18\_flag) \{Serial.print ("AT+HTTPACTION=0 \ | \ r\ |); \\
while(Serial.available()>0){if(Serial.find("OK"))test18_flag=0;}delay(1000);}
lcd.clear();lcd.print("ACTION COMPLETED");delay(5000);
lcd.clear();lcd.print("GET THE DATA");
boolean test19_flag=1; while(test19_flag){Serial.print("AT+HTTPREAD\r\n");
SeriallEvent();
while (Serial.available ()>0) \{ if (Serial.find ("OK")) test 19\_flag=0; \} delay (1000); \}
lcd.clear();lcd.print("DATA OK");delay(5000);
if(temp==1){
check();
temp=0;
i=0;
delay(100);
}}
void SeriallEvent() {
while(Serial.available()) {
if(Serial.find("?ID=")){
digitalWrite(led, HIGH);
delay(100);
digitalWrite(led, LOW);
while (Serial.available()) {
char inChar=Serial.read();
str[i++]=inChar;
if(inChar=='$'){
temp=1;
return;
} } }}
void check(){
if(!(strncmp(str,"ON",2))){lcd.setCursor(1,1);lcd.print("MOTOR ON");delay(500);digitalWrite(motor,HIGH);}
else if(!(strncmp(str,"OFF",3))){lcd.setCursor(1,1);lcd.print("MOTOR OFF");digitalWrite(motor,LOW);}
}
```

```
void gsm_init(){
lcd.clear();lcd.print("GSM TESTING..");
boolean at_flag=1; while(at_flag){Serial.println("AT"); while(Serial.available()>0){if(Serial.find("OK"))at_flag=0;}delay(1000);}
lcd.clear();lcd.print("GSM CONNECTED");delay(1000);lcd.clear();
lcd.print("ECHO");
boolean echo_flag=1;
while(echo_flag)
{Serial.println("ATE0"); while(Serial.available()>0){if(Serial.find("OK"))echo_flag=0;}delay(1000);}
lcd.clear(); lcd.print("Echo OFF");delay(1000);lcd.clear();
lcd.print("Finding Network..");
boolean net_flag=1; while(net_flag){Serial.println("AT+CPIN?");
while(Serial.available()>0){if(Serial.find("+CPIN: READY"))net_flag=0;}delay(1000);}
lcd.clear();lcd.print("Network Found..");
lcd.setCursor(0,1);lcd.print("GSM NETWORK OK");delay(2000);lcd.clear();
lcd.clear();lcd.print("TEST MESS");
boolean test_flag=1; while(test_flag){Serial.println("AT+CMGF=1");
while(Serial.available()>0){if(Serial.find("OK"))test_flag=0;}delay(1000);}
lcd.clear();lcd.print("TEST MESSAGE");delay(1000);
lcd.clear();lcd.print("AT+CGATT");
boolean test1_flag=1; while(test1_flag){Serial.println("AT+CGATT=1");
while(Serial.available()>0){if(Serial.find("OK"))test1_flag=0;}delay(1000);}
lcd.clear();lcd.print("AT+CGATT=1");delay(1000);
lcd.clear();lcd.print("GPRS START");
boolean test2_flag=1;while(test2_flag){Serial.print("AT+SAPBR=3,1,\"CONTYPE\",\"GPRS\"\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test2_flag=0;}delay(1000);}
lcd.clear();lcd.print("GPRS START1");delay(1000);
lcd.clear();lcd.print("GPRS START");
boolean test3_flag=1; while(test3_flag){Serial.print("AT+SAPBR=3,1,\"APN\",\"internet\"\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test3_flag=0;}delay(1000);}
lcd.clear();lcd.print("GPRS START2");delay(1000);
lcd.clear();lcd.print("GPRS MAIN");
boolean test4_flag=1; while(test4_flag){Serial.print("AT+SAPBR=1,1\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test4_flag=0;}delay(1000);}
lcd.clear();lcd.print("GPRS FIND");delay(1000);
lcd.clear();lcd.print("HTTP STARTS");
boolean test5_flag=1; while(test5_flag){ Serial.print("AT+HTTPINIT\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test5_flag=0;}delay(1000);}
lcd.clear();lcd.print("HTTP STARTS1");delay(1000);
lcd.clear();lcd.print("HTTP STARTS");
boolean\ test6\_flag=1; while (test6\_flag) \{Serial.print ("AT+HTTPPARA=\"CID\",1\r\n"); \\
while(Serial.available()>0){if(Serial.find("OK"))test6_flag=0;}delay(1000);}
lcd.clear();lcd.print("HTTP STARTS2");delay(1000);
}
```