
ASSIGNMENT - 1 HOME AUTOMATION

NAME: KEERTHIKA J

ROLL NO: 113119UG03048

CIRCIUT:



CODE:

```
#include <Servo.h>int
dist = 0;
long readUltrasonicDistance(int triggerPin, int echoPin)
{
    pinMode(triggerPin, OUTPUT); / Clear the trigger
    digitalWrite(triggerPin, LOW); delayMicroseconds(2);
    / Sets the trigger pin to HIGH state for 10 microsecondsdigitalWrite(triggerPin, HIGH);
    delayMicroseconds(10);
    digitalWrite(triggerPin, LOW);
    pinMode(echoPin, INPUT);
    / Reads the echo pin, and returns the sound wave travel time inmicroseconds
    return pulseIn(echoPin, HIGH);
}
```

```
Servo servo_8;void
setup()
  servo_8.attach(8, 500, 2500);
  pinMode(2, INPUT);
  pinMode(12, OUTPUT);
  pinMode(A0, INPUT);
  pinMode(9, OUTPUT);
 void loop()
  dist = 0.01723 * readUltrasonicDistance(7, 7);if
  (dist <= 100) \{
   servo_8.write(90);
   delay(1000); / Wait for 1000 millisecond(s)
  } else {
   servo_8.write(0);
   delay(1000); / Wait for 1000 millisecond(s)
  if (digitalRead(2) == 1) {
   digitalWrite(12, HIGH);
   delay(1000); / Wait for 1000 millisecond(s)
  } else {
   digitalWrite(12, LOW);
   delay(1000); / Wait for 1000 millisecond(s)
```

```
if (analogRead(A0) > 200) {
    digitalWrite(9, HIGH);
    delay(1000); / Wait for 1000 millisecond(s)
} else {
    digitalWrite(9, LOW);
    delay(1000); / Wait for 1000 millisecond(s)
}
```

TINKERCAD LINK:

https://www.tinkercad.com/things/71V68hGU W5V-neat-tumeloluulia/editel?sharecode=I8Q0lPz33Wtv2RUkav arscqH8ZiVImQJyo46hjCYMrQ