DEPARTMENT OF ELECTRONICS AND COMMUNICATION ENGINEERING IBM NALAIYA THIRAN PROJECT

Project Development Phase

Date	21 October 2022
Team ID	PNT2022TMID03510
Project Name	IoT Based Smart Crop Protection System for Agriculture
Maximum Marks	8 Marks

Sprint 1:

To publish and access sensor parameters like Temperature, Humidity, and Soil Moisture to the IBM IoT platform.

Solution C++ Coding:

```
#include <LiquidCrystal.h>
LiquidCrystal lcd(8,9,10,11,12,13);//rs,en,data pins d4 -d7
float TEMP; int MOISURE, HUM;
const int buzzer=6; const int
motor=7;
led=4,temp=0,i=0;
                        char
str[30];
              int
                       aa=0,
dt=0////temp; int dh=0;///hum
int s1=0, s3=0; void setup() {
lcd.begin(16,2);
Serial.begin(9600);
pinMode(buzzer, OUTPUT);
pinMode(motor, OUTPUT);
digitalWrite(buzzer, LOW);
digitalWrite(motor, LOW);
lcd.clear();
lcd.setCursor(0,0);lcd.print("IOT Based ");
lcd.setCursor(0,1);lcd.print("Agriculture Crop"); delay(5000);lcd.clear();
lcd.setCursor(0,0);lcd.print("Field Monitoring");
lcd.setCursor(0,1);lcd.print("Irrigation"); delay(5000);lcd.clear();
lcd.setCursor(0,0);lcd.print(" Automation");
lcd.setCursor(0,1);lcd.print("using GPRS ");
delay(5000);lcd.clear();
gsm_init();lcd.clear(); digitalWrite(buzzer,
LOW); digitalWrite(motor, LOW);
} void loop()
\{aa=aa+1;
digitalWrite(buzzer, LOW);
lcd.clear();
TEMP = analogRead(0);
```

```
TEMP=(TEMP*500)/1023;
lcd.setCursor(0,0);lcd.print("T:");lcd.setCursor(3,0);lcd.print(TEMP);delay(200);if(TEMP<50){dt=0;delay(100);}
if(TEMP>50){dt=dt+1; if(dt==2){}}
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);lcd.clear();send_gprs();delay(500);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
lcd.clear();lcd.setCursor(0,0);lcd.print("SENDING SMS");lcd.setCursor(0,1);lcd.print("TEMP ALERT");
Serial.println("AT+CMGF=1");delay(400);
Serial.println("AT+CMGS=\"9148300815\"");delay(400);
Serial.println("Over Temperature\n");delay(100);
Serial.print("Temp=");delay(100);Serial.print(TEMP);delay(500);Serial.write(26);delay(500);
Serial.print("AT\r\n");delay(1000);Serial.print("AT\r\n");delay(1000);Serial.print("AT+CMGF=1");delay(1000);} }}
HUM= analogRead(1);HUM =HUM/2; HUM=HUM+12;
lcd.setCursor(0,1);lcd.print("H:");lcd.setCursor(3,1);lcd.print(HUM);delay(2500);if(HUM<30){dh=0;delay(100);}
if(HUM>45){dh=dh+1; if(dh==2){}}
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);lcd.clear();send_gprs();delay(500);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
lcd.clear();lcd.setCursor(0,0);lcd.print("SENDING SMS");lcd.setCursor(0,1);lcd.print("HUMIDITY ALERT");
Serial.println("AT+CMGF=1");delay(400);
Serial.println("AT+CMGS=\"9148300815\"");delay(400);
Serial.println("HUMIDITY ALERT\n");delay(100);
Serial.print("HUM=");delay(100);Serial.print(HUM);delay(500);Serial.write(26);delay(500);
Serial.print("AT\r\n");delay(1000);Serial.print("AT\r\n");delay(1000);Serial.print("AT+CMGF=1");delay(1000);} }}
MOISURE = analogRead(2); MOISURE= MOISURE/4; MOISURE=256-MOISURE;
lcd.setCursor(9,0);
lcd.print("M: ");
lcd.setCursor(11,0);
lcd.print(MOISURE);
delay(500);
if(MOISURE<100){
s1=s1+1; if(s1==5){
s3=0;
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);lcd.clear();send_gprs();delay(500);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
lcd.clear();lcd.setCursor(0,0);lcd.print("SENDING SMS");delay(2000); lcd.clear();
lcd.setCursor(0,0);lcd.print("FEILD AT DRY");
lcd.setCursor(0,1);lcd.print("MOTOR ON");delay(2000); digitalWrite(motor,
HIGH):
Serial.print("AT\r\n");delay(2000);Serial.print("AT\r\n");delay(2000);
Serial.println("AT+CMGF=1");delay(400);Serial.println("AT+CMGS=\"9148300815\"");delay(400); // use your 10 digit cell no. here
Serial.println("FEILD AT DRY\n");delay(100);
```

```
Serial.println("MOTOR ON\n");delay(100);
Serial.write(26);delay(100);
Serial.print("AT\r\n");delay(1000);Serial.print("AT\r\n");delay(1000);Serial.println("AT+CMGF=1");delay(1000);
motor_gprs(); delay(2000); pump_gprs(); delay(2000);
} delay(100);
if(MOISURE>200){
s3=s3+1; if(s3==5){
s1=0;
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);lcd.clear();send_gprs();delay(500);
delay(200);digitalWrite(buzzer, HIGH);delay(200);digitalWrite(buzzer, LOW);
lcd.clear();lcd.setCursor(0,0);lcd.print("SENDING SMS");delay(2000); lcd.clear();
lcd.setCursor(0,0);lcd.print("FEILD AT WET");
lcd.setCursor(0,1);lcd.print("MOTOR OFF");delay(2000);digitalWrite(motor, LOW);
Serial.print("AT\r\n"); delay(2000); Serial.print("AT\r\n"); delay(2000);
Serial.println("AT+CMGF=1");delay(400);Serial.println("AT+CMGS=\"9148300815\"");delay(400); // use your 10 digit cell no. here
Serial.println("FEILD AT WET\n");delay(100);
Serial.println("MOTOR OFF\n");delay(100);
Serial.write(26);delay(100);
Serial.print("AT\r\n");delay(1000);Serial.print("AT\r\n");delay(1000);Serial.println("AT+CMGF=1");delay(1000);
motor_gprs(); delay(2000); pump_gprs(); delay(2000);
} delay(100);
if(aa==10)
lcd.clear();
send_gprs();
delay(2000);
pump_gprs();
delay(2000);
aa=0; }}
void motor_gprs(){
lcd.clear();lcd.print("GPRS SENDING"); boolean
test47_flag=1;
while(test47_flag){Serial.print("AT+HTTPPARA=\"URL\",\"http://iotbabycare.com/iot_green_agrimnr/put_motor.php?mot=motor");
Serial.print("\"");Serial.print("\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test47_flag=0;}delay(1000);}
lcd.clear();lcd.print("SENT COMPLETED");delay(10000);lcd.clear() lcd.clear();lcd.print("ACTION");
boolean test48_flag=1; while(test48_flag){Serial.print("AT+HTTPACTION=0\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test48_flag=0;}delay(1000);}
lcd.clear();lcd.print("SEND OK");delay(2000); delay(2000);delay(2000);
boolean at_flagd=1; while(at_flagd) {Serial.println("AT"); while(Serial.available()>0) {if(Serial.find("OK"))at_flagd=0;} delay(1000);}
}
void send_gprs(){
```

```
lcd.clear();lcd.print("GPRS SENDING"); boolean
test7_flag=1;
while(test7_flag){Serial.print("AT+HTTPPARA=\"URL\",\"http://iotbabycare.com/iot_green_agrimnr/put_data.php");
Serial.print("?temp=");Serial.print(TEMP);
Serial.print("&hum=");Serial.print(HUM);
Serial.print("&mos=");Serial.print(MOISURE); Serial.print("\"");Serial.print("\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test7_flag=0;}delay(1000);}
lcd.clear();lcd.print("SENT COMPLETED");delay(10000);lcd.clear(); lcd.clear();lcd.print("ACTION");
boolean test8_flag=1; while(test8_flag){Serial.print("AT+HTTPACTION=0\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test8_flag=0;}delay(1000);}
lcd.clear();lcd.print("SEND OK");delay(2000); delay(2000);delay(2000);
}
void pump_gprs(){
boolean at_flagd=1;while(at_flagd){Serial.println("AT");while(Serial.available()>0){if(Serial.find("OK"))at_flagd=0;}delay(1000);}
lcd.clear();lcd.print("PING TO WEBSITE");
boolean
test17_flag=1;while(test17_flag){Serial.print("AT+HTTPPARA=\"URL\",\"http://iotbabycare.com/iot_green_agrimnr/get_data.php");Serial.prin
t("\");Serial.print("\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test17_flag=0;}delay(1000);}
lcd.clear();lcd.print("WEBLINK
                                                     SUCESS");delay(1000);
lcd.clear();lcd.print("HTTP ACTION");
boolean test18_flag=1; while (test18_flag) { Serial.print("AT+HTTPACTION=0\rdot r");
while(Serial.available()>0){if(Serial.find("OK"))test18_flag=0;}delay(1000);}
lcd.clear();lcd.print("ACTION COMPLETED");delay(5000); lcd.clear();lcd.print("GET
THE DATA");
boolean\ test19\_flag=1; while (test19\_flag) \{Serial.print ("AT+HTTPREAD \ "\ "); Seriall Event (); \\
while(Serial.available()>0){if(Serial.find("OK"))test19_flag=0;}delay(1000);}
lcd.clear();lcd.print("DATA OK");delay(5000); if(temp==1){ check();
temp=0; i=0; delay(100);
void SeriallEvent() {
while(Serial.available()) {
if(Serial.find("?ID=")){
digitalWrite(led, HIGH); delay(100);
digitalWrite(led, LOW);
while (Serial.available()) {
char inChar=Serial.read();
str[i++]=inChar;
if(inChar=='$'){ temp=1;
return:
} } } }
void check(){
if(!(strncmp(str,"ON",2))){lcd.setCursor(1,1);lcd.print("MOTOR ON");delay(500);digitalWrite(motor,HIGH);} else
if(!(strncmp(str,"OFF",3))){lcd.setCursor(1,1);lcd.print("MOTOR OFF");digitalWrite(motor,LOW);}
```

```
}
void gsm_init(){
lcd.clear();lcd.print("GSM TESTING..");
boolean at_flag=1; while(at_flag){Serial.println("AT"); while(Serial.available()>0){if(Serial.find("OK"))at_flag=0;}delay(1000);}
lcd.clear();lcd.print("GSM CONNECTED");delay(1000);lcd.clear(); lcd.print("ECHO"); boolean echo_flag=1; while(echo_flag)
{Serial.println("ATE0"); while(Serial.available()>0){if(Serial.find("OK"))echo_flag=0;}delay(1000);}
lcd.clear(); lcd.print("Echo OFF");delay(1000);lcd.clear(); lcd.print("Finding Network..");
boolean net_flag=1; while(net_flag){Serial.println("AT+CPIN?");
while(Serial.available()>0){if(Serial.find("+CPIN: READY"))net_flag=0;}delay(1000);} lcd.clear();lcd.print("Network
Found..");
lcd.setCursor(0,1);lcd.print("GSM NETWORK OK");delay(2000);lcd.clear(); lcd.clear();lcd.print("TEST
MESS");
boolean test_flag=1; while(test_flag){Serial.println("AT+CMGF=1");
while(Serial.available()>0){if(Serial.find("OK"))test_flag=0;}delay(1000);}
lcd.clear();lcd.print("TEST MESSAGE");delay(1000); lcd.clear();lcd.print("AT+CGATT");
boolean test1_flag=1; while(test1_flag){Serial.println("AT+CGATT=1");
while(Serial.available()>0){if(Serial.find("OK"))test1_flag=0;}delay(1000);}
lcd.clear();lcd.print("AT+CGATT=1");delay(1000); lcd.clear();lcd.print("GPRS
START");
boolean test2_flag=1; while(test2_flag){Serial.print("AT+SAPBR=3,1,\"CONTYPE\",\"GPRS\"\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test2_flag=0;}delay(1000);}
lcd.clear();lcd.print("GPRS START1");delay(1000); lcd.clear();lcd.print("GPRS START");
boolean test3_flag=1; while(test3_flag){Serial.print("AT+SAPBR=3,1,\"APN\",\"internet\"\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test3_flag=0;}delay(1000);}
lcd.clear();lcd.print("GPRS START2");delay(1000); lcd.clear();lcd.print("GPRS MAIN");
boolean test4_flag=1; while (test4_flag) { Serial.print("AT+SAPBR=1,1\r\n");
while(Serial.available()>0){if(Serial.find("OK"))test4_flag=0;}delay(1000);}
lcd.clear();lcd.print("GPRS FIND");delay(1000); lcd.clear();lcd.print("HTTP
STARTS");
boolean\ test5\_flag=1; while (test5\_flag) \{Serial.print("AT+HTTPINIT\r\n"); \\
while(Serial.available()>0){if(Serial.find("OK"))test5_flag=0;}delay(1000);}
lcd.clear();lcd.print("HTTP STARTS1");delay(1000); lcd.clear();lcd.print("HTTP
STARTS");
boolean\ test6\_flag=1; while (test6\_flag) \{Serial.print ("AT+HTTPPARA=\"CID\",1\r\n"); \\
while(Serial.available()>0){if(Serial.find("OK"))test6_flag=0;}delay(1000);}
lcd.clear();lcd.print("HTTP STARTS2");delay(1000);}
```