Project Development Phase

SMART WASTE MANAGEMENT SYSTEM FOR METROPOLITAN CITIES

TEAM ID: PNT2022TMID39310

TEAM MEMBERS

ROLE	TEAM MEMBERS NAME	ROLL NO
TEAM LEADER	RUBESH .S	(422619104035)
TEAM MEMBER 1	ABIRAMI .S	(422619104002)
TEAM MEMBER 2	HARITHA .S	(422619104016)
TEAM MEMBER 3	TAMIZHSELVAN .D	(422619104044)

Project Development - Delivery Of Sprint-4

Sprint	Functional Requirement (Epic)	User Story Number	User Story / Task	Story Points	Priority	Team Members
Sprint-4	Develop A Web Application Using Node-RED Service	USN- 8	Create Node Red Flow To Get Data From Device	10	High	S.Rubesh S.Haritha
Sprint-4	Develop A Web Application Using Node-RED Service	USN- 9	UI Nodes Installation	10	Medium	S.Abirami D.Tamizhselvan

Delivery

Sprint	Total Story Points	Duration	Sprint Start Date	Sprint End Date (Planned)	Story Points Completed (as on Planned End Date)	Sprint Release Date (Actual)
Sprint-4	20	6 Days	14 Nov 2022	19 Nov 2022	20	19 Nov 2022

Create Node Red Flow To Get Data From Device

Task Assigned: S.Rubesh,S.Haritha

Task Started On: 14 Nov 2022

Task Completion Date: 15 Nov 2022

Create Node Red Flow To Get Data From Device






Node-RED
Deploy
Flow 1
storage
cloudant in
cloudant out
Edit function node
Delete
Cancel
Done
Properties
Name
Weight
Setup
On Start
On Message
On Stop
1 msg.payload=msg.payload.weight;
2 return msg;
Enabled
help
delay
function
html
http in
function
A JavaScript function to run against the messages being received by the node.
The messages are passed in as a JavaScript object called msg.
By convention it will have a msg.payload property containing the body of the message.
The function is expected to return a message object (or multiple message objects), but can choose to return nothing in order to halt a flow.
The On Start tab contains code that will be


Node-RED
Deploy
Flow 1
storage
cloudant in
cloudant out
Edit worldmap node
Delete
Cancel
Done
Properties
Group
[Smart Waste Monitoring] Default
Size
auto
Start
Latitude
Longitude
Zoom
1 - 18
Map list
7 selected
Base map
OpenStreetMap Greyscale
Overlays
5 selected
Cluster when
zoom level is less than
0 (0:off - 19)
Max age
Remove markers after
600
seconds
Enabled
help
ibmiot out
node-red-contrib-web-worldmap
worldmap
worldmap
worldmap
Plots "things" on a map in Node-RED Dashboard. Needs an internet connection.
It is possible to instantiate multiple worldmap nodes but each one must be given a unique path. Worldmap-in nodes are matched to worldmap nodes by having exactly the same path.
Shortcut -]c[]m - ctrl-shift-m to jump to the default Map (/worldmap).
The minimum msg.payload must contain name, lat and lon properties, e.g.


Node-RED
Deploy
Flow 1
storage
cloudant in
cloudant out
IBM IoT
connected
Edit gauge node
Delete
Cancel
Done
Properties
Group
[Smart Waste Monitoring] Default
Size
auto
Type
Level
Label
Weight
Value format
{{value}}
Units
Kg
Range
min 0
max 1000
Class
Optional CSS class name(s) for widget
Name
Enabled
help
Search help
dropdown
form
gauge
dashboard group
gauge
Adds a gauge type widget to the user interface.
The msg.payload is searched for a numeric value and is formatted in accordance with the defined Value Format, which can then be formatted using Angular filters.
For example : {{value | number:1}}% will round the value to one decimal place and append a % sign.
The colours of each of 3 sectors can be specified and the gauge will blend between them. The colours should be specified in hex


Node-RED
Deploy
Flow 1
storage
cloudant in
cloudant out
IBM IoT
connected
Edit gauge node
Delete
Cancel
Done
Properties
Group
[Smart Waste Monitoring] Default
Size
auto
Type
Gauge
Label
GPS
Value format
{{value}}
Units
Km
Range
min 0
max 100
Colour gradient
Sectors
0
optional
optional
100
Enabled
help
Search help
dropdown
form
gauge
dashboard group
gauge
Adds a gauge type widget to the user interface.
The msg.payload is searched for a numeric value and is formatted in accordance with the defined Value Format, which can then be formatted using Angular filters.
For example : {{value | number:1}}% will round the value to one decimal place and append a % sign.
The colours of each of 3 sectors can be specified and the gauge will blend between them. The colours should be specified in hex


Node-RED
Deploy
Flow 1
storage
cloudant in
cloudant out
IBM IoT
connected
Edit gauge node
Delete
Cancel
Done
Properties
Group
[Smart Waste Monitoring] Default
Size
auto
Type
Gauge
Label
Distance
Value format
{{value}}
Units
centimetre
Range
min 0
max 1000
Colour gradient
Sectors
0
optional
optional
1000
Enabled
help
Search help
dropdown
form
gauge
dashboard group
gauge
Adds a gauge type widget to the user interface.
The msg.payload is searched for a numeric value and is formatted in accordance with the defined Value Format, which can then be formatted using Angular filters.
For example : {{value | number:1}}% will round the value to one decimal place and append a % sign.
The colours of each of 3 sectors can be specified and the gauge will blend between them. The colours should be specified in hex


Node-RED
Deploy
Flow 1
storage
cloudant in
cloudant out
IBM IoT
connected
Edit ibmiot in node
Delete
Cancel
Done
Properties
Authentication
API Key
API Key
188114a0076d65e
Input Type
Device Event
Device Type
All or
Smartgarbagebins
Device Id
All or
Bin1
Event
All or
Format
All or
json
QoS
0
Name
IBM IoT
Enabled
help
Search help
node-red-contrib-scx-ibmiotapp
ibmiot
ibmiot in
ibmiot out
node-red-contrib-web-worldmap
ibmiot in
Input node that can be used with Watson IoT Platform to receive events sent from devices, receive commands sent to devices, or receive status updates concerning devices or applications. It produces an object called msg and sets msg.payload to be a String containing the payload of the incoming message.
The value of "Device Id" is stored in msg.deviceId
The value of "Application Id" is stored in msg.applicationId

CODE:

```
import time
 import sys
 import ibmiotf.application
import ibmiotf.device
import random
import sys
#Provide your IBM Watson Device Credentials
organization = "a7mbs7"
deviceType ="Smartgarbagebins"
deviceId = "Bin1"
authMethod = "token"
authToken = "Sakthi@2001"
# Initialize GPIO
def myCommandCallback(cmd):
print("Command received: %s" % cmd.data['command'])
status=cmd.data['command']
if status =="lighton":
    print("led in on")
    else :
        print ("led is off") try:
    deviceOptions = {"org": organization, "type": deviceType, "id": deviceId,
"authmethod":authMethod, "auth-token": authToken}
    deviceCli = ibmiotf.device.Client(deviceOptions)
#.....
except Exception as e:
    print("Caught exception connecting device: %s" % str(e))
```

```
    sys.exit()
#Connect and send a datapoint "hello" with value "world" into the cloud as an event oftype "greeting" 10 times
deviceCli.connect()
 while True:
    #Get Sensor Data from DHT11
time.sleep(5)
    Ultrasonic=random.randint(0,80)
Weight=random.randint(0,100)
lat = round(random.uniform(11.03, 11.50), 6)
long = round(random.uniform(76.80, 76.90), 6)
GPS = str(lat) + str(',') + str(long)
 myData = {'Ultrasonic' : Ultrasonic, 'Weight'
Weight , 'GPS' : GPS}
  #print data     def
myOnPublishCallback():
       print ("Published Ultrasonic = %s Cm" %Ultrasonic, "Weight:%s kg " %Weight,
"GPS: %s"%GPS)
success = deviceCli.publishEvent("IoTSensor", "json", data=myData, qos=0,
on_publish=myOnPublishCallback)
 if not success:
          print("Not connected to IoTF")
          time.sleep(1)
          deviceCli.commandCallback =
myCommandCallback
```

Disconnect the device and application from

the cloud deviceCli.disconnect()

RESULT:

Thus the Node Red Flow is successfully created and Got Data From the Device.