```
ibmcloud - A command line tool to interact with IBM Cloud
 Find more information at: https://ibm.biz/cli-docs
 [environment variables] ibmcloud [global options] command [arguments...] [command options]
 2.12.1+b8488a1-2022-10-31T15:08:10+00:00
COMMANDS:
 account
              Manage accounts, users, orgs and spaces
 api
              Set or view target API endpoint
 billing
              Retrieve usage and billing information
              Manage catalog
 catalog
              Run Cloud Foundry CLI with IBM Cloud CLI context
 config
              Write default values to the config
              Create, develop, deploy, and monitor applications
 dev
 enterprise
              Manage enterprise, account groups and accounts.
              Manage identities and access to resources
 iam
 login
              Log user in
              Log user out
 logout
 plugin
              Manage plug-ins and plug-in repositories
 regions
              List all the regions
              Manage resource groups and resources
 resource
              List all resources
 resources
              Manage Classic infrastructure services
 target
              Set or view the targeted region, account, resource group, org or space
              Update CLI to the latest version
  update
              Print the version
  version
 help, h
              Show help
Enter 'ibmcloud help [command]' for more information about a command.
ENVIRONMENT VARIABLES:
 IBMCLOUD COLOR=false
                                          Do not colorize output
 IBMCLOUD VERSION CHECK=false
                                          Do not check latest version for update
 IBMCLOUD HTTP TIMEOUT=5
                                          A time limit for HTTP requests
 IBMCLOUD API KEY=api key value
                                          API Key used for login
 IBMCLOUD CR VPC URL=url value
                                          The custom server URL to use when obtaining an instance identity token and IAM token as a VPC VSI compute resource. This valu
 will replace the default server endpoint of the VPC VSI instance identity token service.
                                          Compute resource token used for login. Can either be a token string or a path to a @file.
 IBMCLOUD CR TOKEN=cr token value
  IBMCLOUD CR PROFILE=profile value
                                          The name, ID, or CRN of the linked trusted IAM profile to be used when obtaining the IAM access token. If authenticating as a
```