


Charity shop

Choose food to donate to the local homeless shelter



Complete your order!

- First page, allows the user to choose which food to order
- Uses a bootstrap grid system, each food is a different grid. The size of the grid depends on the size of the screen, medium and large screen make each grid take 2 out of 12 spaces per row. Small screens make each grid take up all 12 spaces at once
- The footer is a button that hides the display of the grid and displays the next page instead

Charity shop

Choose food to donate to the local homeless shelter

Cart:

Spaghetti: 10€; Kebab: 15€; Herring: 10€;

Total:

37€

Total with discount (More than 3 products):

27€

[Return](#) [Checkout](#)

Charity shop

Choose food to donate to the local homeless shelter

Cart:

Herring: 10€; Steak: 25€;

Total:

35€

Total with discount (More than 3 products):

No discount

[Return](#) [Checkout](#)

- Second page, shows the ordered products using headers
- If the user has ordered more than 3 products, then a 10 euro discount is applied to the total, otherwise “No discount is written”
- The footer includes 2 buttons, Return displays the first page again, Check out displays the info form instead

Charity shop
Choose food to donate to the local homeless shelter

Personal info

Email address
Name@gmail.com

Name
Martin Dotzov

Phone Number (optional)
123-456-7890

Address

City
Krems

Country
Austria

Zip code
Zip Code

Return **Finalise**

The screenshot shows a charity donation form with a blue header and footer. The main content area has a white background. It includes sections for personal information (Email address, Name, Phone number) and address (City, Country, Zip code). Buttons for 'Return' and 'Finalise' are at the bottom right.

- Third page, shows a bootstrap form for the user's personal info
- Email address, name and city are a text input type, the phone number is a number input type and the zip code is a tel input type
- The zip code has a max length of 6 characters The country field is a drop down menu, allowing the user to pick from 5 countries (Austria, Germany, UK, Spain, Bulgaria)
- The footer includes 2 buttons like the previous, return displays the second page again, finalise shows the final page

Charity shop

Choose food to donate to the local homeless shelter

Thank you for your donation!

- Final page, just a simple header to show to the user that the transaction is complete