VIDEO_FREEZE

System Message: ERROR/3 (`D:\onboarding-resources\sample-onboarding-resources\linux-master\drivers\staging\media\av7110\[linux-master][drivers][staging][media][av7110]video-freeze.rst`**, line 2)**

Unknown directive type "c:namespace".

```
.. c:namespace:: DTV.video
```

Name

VIDEO_FREEZE

Attention!

This ioctl is deprecated.

Synopsis

System Message: ERROR/3 (`D:\onboarding-resources\sample-onboarding-resources\linux-master\drivers\staging\media\av7110\[linux-master][drivers][staging][media][av7110]video-freeze.rst`**, line 20)**

Unknown directive type "c:macro".

```
.. c:macro:: VIDEO_FREEZE
```

```
int ioctl(fd, VIDEO_FREEZE)
```

Arguments

System Message: ERROR/3 (`D:\onboarding-resources\sample-onboarding-resources\linux-master\drivers\staging\media\av7110\[linux-master][drivers][staging][media][av7110]video-freeze.rst`**, line 27)**

Unknown directive type "flat-table".

```
.. flat-table::
    :header-rows:  0
    :stub-columns: 0

    -  .. row 1

        -  int fd

        -  File descriptor returned by a previous call to open().

    -  .. row 2

        -  int request

        -  Equals VIDEO_FREEZE for this command.
```

Description

This ioctl is for Digital TV devices only. To control a V4L2 decoder use the V4L2 :ref:`VIDIOC_DECODER_CMD` instead.

System Message: ERROR/3 (`D:\onboarding-resources\sample-onboarding-resources\linux-master\drivers\staging\media\av7110\[linux-master][drivers][staging][media][av7110]video-freeze.rst`**, line 46); *backlink***

Unknown interpreted text role "ref".

This ioctl call suspends the live video stream being played. Decoding and playing are frozen. It is then possible to restart the decoding and playing process of the video stream using the VIDEO_CONTINUE command. If VIDEO_SOURCE_MEMORY is selected in the ioctl call VIDEO_SELECT_SOURCE, the Digital TV subsystem will not decode any more data until the ioctl call VIDEO_CONTINUE or VIDEO_PLAY is performed.

Return Value

On success 0 is returned, on error -1 and the `errno` variable is set appropriately. The generic error codes are described at the :ref:`Generic Error Codes <gen-errors>` chapter.

> **System Message: ERROR/3** (`D:\onboarding-resources\sample-onboarding-resources\linux-master\drivers\staging\media\av7110\[linux-master][drivers][staging][media][av7110]video-freeze.rst`, **line 59);** *backlink*
>
> Unknown interpreted text role "ref".