Image

Besides the native features of img, support lazy load, custom placeholder and load failure, etc.

Basic Usage

:::demo Indicate how the image should be resized to fit its container by fit , same as native object-fit.

```
<div class="demo-image">
 <div class="block" v-for="fit in fits" :key="fit">
    <span class="demonstration">{{ fit }}</span>
   <el-image
     style="width: 100px; height: 100px"
     :src="url"
     :fit="fit"></el-image>
  </div>
</div>
<script>
 export default {
   data() {
     return {
       fits: ['fill', 'contain', 'cover', 'none', 'scale-down'],
'https://fuss10.elemecdn.com/e/5d/4a731a90594a4af544c0c25941171jpeg.jpeg'
    }
 }
</script>
```

:::

Placeholder

:::demo Custom placeholder content when image hasn't loaded yet by slot = placeholder

```
export default {
    data() {
        return {
            src: 'https://cube.elemecdn.com/6/94/4d3ea53c084bad6931a56d5158a48jpeg.jpeg'
        }
     }
}
</script>
```

...

Load Failed

:::demo Custom failed content when error occurs to image load by slot = error

:::

Lazy Load

:::demo Use lazy load by <code>lazy = true</code> . Image will load until scroll into view when set. You can indicate scroll container that adds scroll listener to by <code>scroll-container</code> . If undefined, will be the nearest parent container whose overflow property is auto or scroll.

```
'https://fuss10.elemecdn.com/d/e6/c4d93a3805b3ce3f323f7974e6f78jpeg.jpeg',
    'https://fuss10.elemecdn.com/3/28/bbf893f792f03a54408b3b7a7ebf0jpeg.jpeg',
    'https://fuss10.elemecdn.com/2/11/6535bcfb26e4c79b48ddde44f4b6fjpeg.jpeg'
    ]
    }
}
</script>
```

:::

Image Preview

:::demo allow big image preview by setting previewSrcList prop.

```
<div class="demo-image__preview">
 <el-image
  style="width: 100px; height: 100px"
   :src="url"
   :preview-src-list="srcList">
 </el-image>
</div>
<script>
 export default {
   data() {
     return {
      url:
'https://fuss10.elemecdn.com/e/5d/4a731a90594a4af544c0c25941171jpeg.jpeg',
       srcList: [
         'https://fuss10.elemecdn.com/8/27/f01c15bb73e1ef3793e64e6b7bbccjpeg.jpeg',
         'https://fuss10.elemecdn.com/1/8e/aeffeb4de74e2fde4bd74fc7b4486jpeg.jpeg'
       ]
     }
   }
 }
</script>
```

:::

Attributes

Attribute	Description	Туре	Accepted values	Default
src	Image source, same as native	string	_	-
fit	Indicate how the image should be resized to fit its container, same as <u>object-fit</u>	string	fill / contain / cover / none / scale-down	-

alt	Native alt	string	-	-
referrer- policy	Native referrerPolicy	string	-	-
lazy	Whether to use lazy load	boolean	_	false
scroll- container	The container to add scroll listener when using lazy load	string / HTMLElement	_	The nearest parent container whose overflow property is auto or scroll
preview- src-list	allow big image preview	Array	_	-
z-index	set image preview z-index	Number	_	2000

Events

Event Name	Description	Parameters
load	Same as native load	(e: Event)
error	Same as native error	(e: Error)

Slots

Slot Name	Description	
placeholder	Triggers when image load	
error	Triggers when image load failed	