Network Manager Release Notes

Version 2.3

IQGeo, NINE Hills Road, Cambridge, CB2 IGE, United Kingdom.

Telephone: +44 (0) 1223 606655. Website: https://www.iqgeo.com/.

Contents

1: Introduction ... 3
1.1 Intended Audience ... 3
2: Installation ... 4
2.1 Prerequisites ... 4
2.2 Installing the Software ... 4
2.3 Creating a New Database ... 4
2.4 Upgrading an Existing Database ... 5
3: End-user GUI Changes ... 6
3.1 Tools Palette ... 6
3.2 Managing User Groups ... 6
3.2.1 Importing User Groups ... 7
3.2.2 Adding or Editing User Groups ... 8
3.2.2.1 Adding a User Group ... 8
3.2.2.2 Editing a User Group ... 10
3.3 Working with Designs ... 12
3.3.1 Listing Design Objects ... 13
4: Administrator GUI Changes ... 16
4.1 Configuration Settings Page ... 16
4.2 Roles Configuration Page ... 17
4: Tools ... 18
5: Data Model Changes ... 19
6: Upgrading ... 20
6.1 Upgrading Your Database ... 20

1: Introduction

This document provides a summary of the major changes in this release of Network Manager for Telecoms.

1.1 Intended Audience

This document is intended for Administrators and Developers with a detailed technical knowledge of IQGeo Platform and utilities.

2: Installation

The following changes relate to installation and upgrade.

2.1 Prerequisites

Component	Version	Comments
IQGeo Platform	6.3	Mandatory
IQGeo Workflow Module	6.3	Mandatory
IQGeo Anywhere	6.3 (or higher)	Optional

All components must include any released patches.

2.2 Installing the Software

1. Uncompress the software download and copy the **comms** folder into:

   ```
   <myWorld_install_dir>/WebApps/myworldapp/modules
   ```

2. Download the module's JavaScript dependencies:

   ```
   myw_product fetch node_modules
   ```

3. Rebuild your JavaScript bundles:

   ```
   myw_product build applications
   ```

2.3 Creating a New Database

If you do not already have an IQGeo database, or that database does not yet have the Network Manager tables installed, you will need to:

- Install the Network Manager tables.
- Configure the network object types for your installation.

These processes are covered in detail in the *Installation and Configuration Guide*.

2.4 Upgrading an Existing Database

If you already have a Network Manager database from a previous release, you will need to:

- Upgrade your database.
- Perhaps perform some post-upgrade configuration changes.

These processes are covered in detail in *Upgrading* on page 20.

3: End-user GUI Changes

3.1 Tools Palette

User group manager control has been added to the Tools palette.

Figure 3-1: Tools Palette - User Groups Tool

3.2 Managing User Groups

The group owner can add, edit, or import user groups from within the application.

1. Click the **User Groups** tool 

from the **Tools Palette** display. A dialog is then displayed.



Figure 3-2: User Groups Dialog

You can now import a list of users, add a new user group or edit an existing user group.

3.2.1 Importing User Groups

From the **User Groups** dialog, you can import a .csv list of users for a one-time bulk import.

To do this, click the **Import** button.



Figure 3-3: User Groups Dialog - Import Button

You can now import the .csv file from the location where it is saved on your device. The user group details from the .csv files are then shown on the dialog.



Figure 3-4: User Groups Dialog - User Groups from .csv File Displayed

3.2.2 Adding or Editing User Groups

From the **User Groups** dialog, you can add new user groups or edit existing user groups.

3.2.2.1 Adding a User Group

1. Click the **Add User Group** button.



Figure 3-5: User Groups Dialog - Add User Group Button

Another dialog then opens on which you can add the details of a new user group.



Figure 3-6: Create User Group Dialog

> You must know the exact user name to add a member in the **Create User Group** dialog.

Once you have entered the details:

2. Click the **Save** button. You are then returned to the **User Groups** dialog where the new user group is now listed.

3.2.2.2 Editing a User Group

1. Click the pencil icon next to the user group you wish to edit.



Figure 3-7: User Groups Dialog - Pencil Icon

Another dialog then opens.



Figure 3-8: Editing a User Group

2. Edit the description or add or delete users from the group.

> You must know the exact user name to add a member in the **Create User Group** dialog.

Once you have edited the details:

3. Click the **Update** button. You are then returned to the **User Groups** dialog where the new user group is now listed.

3.3 Working with Designs

When you add a new design, you can set the attributes for the design in the **Details** tab.

The **Group** drop down list allows group owners and design owners to restrict who can access a design by assigning a design to a user group. This enables you to track changes that users make to designs.



Figure 3-9: Group Drop Down List

The design is now restricted to the assigned group and the group owner. Members of any other group will not be able to view it.

When you click **Save**, the design is created and you can see the group to which the design has been allocated.



Figure 3-10: Design Toolbar

3.3.1 Listing Design Objects

You can either view **all** changes in a design or you can view the design changes by user.

To view a list of objects that are in a design:

1. Open the design.

2. In the **Design** toolbar, click the **Select objects** icon.



Figure 3-11: Select Objects icon

The following two options, **System** and **User** are then displayed in a drop down list.



Figure 3-12: Select Objects - System or User

If you select **System**, the **Details** panel displays the list of **all** objects in the design.

If you select **User** from the drop down list, you can filter the list of objects in the **Details** panel to display objects belonging either to all users or to one or more specific users.

A window is displayed in which you can either select all users (**Check All**) or one or more specific users by enabling the check box beside their name.

Figure 3-13: Select Users To Filter

3. Click **OK** to clear the window and go back to the **Details** panel. The list of objects then shows only those belonging to the selected users.



Figure 3-14: List of Objects Filtered by User

4: Administrator GUI Changes

4.1 Configuration Settings Page

The **User Group** field on the **Configuration > Settings** page **> Designs** item, is used for managing user groups.



Figure 4-1: Configuration > Settings > Designs item > User Group Field

The right to edit user groups can be assigned to specific roles. These are managed on the **Roles Configuration** page.

4.2 Roles Configuration Page

The following right has been added:

Edit User Groups - Users whose roles have this right will be able to manage user groups and users who have this right will be able to open and edit.

Comms: Edit master- Additionally, users whose roles have this right will be able to open and edit a design regardless of the design group assignment.

For more information, see the *Installation and Configuration Guide*.

4: Tools

Missing Connections category added to *comms_db <db> validate <category>* command.

5: Data Model Changes

New system feature added: *mywcom_change_detail*.

The **user_group** field has been added to all feaures that are registered as design objects.

6: Upgrading

This section provides an overview of the upgrade process for this release.

6.1 Upgrading Your Database

To upgrade from the previous release of Network Manager:

1. Apply all IQGeo Platform upgrades:

```
myw_db <db_name> upgrade core 630
```

2. Apply the Network Manager upgrade:

```
myw_db <db_name> upgrade comms 6323
```

3. Perform the post upgrade actions listed below.

Copyright © 2022, IQGeo UK Ltd. IQGeo is a registered ® trademark. All Rights Reserved. You may not reproduce this document in whole or in part without permission in writing from IQGeo at the following address:

IQGeo UK Ltd.

NINE Hills Road

Cambridge, CB2 IGE

United Kingdom

Tel: +44 (0) 1223 606655

E-mail: support@iqgeo.com

WWW: https://www.iqgeo.com/

All contents of this document are subject to change without notice and do not represent a commitment on the part of IQGeo. Reasonable effort is made to ensure the accuracy of the information contained in the document. However, due to on-going product improvements and revisions, IQGeo and its subsidiaries do not warrant the accuracy of this information and cannot accept responsibility for errors or omissions that may be contained in this document.

Information in this document is provided in connection with IQGeo products. No license, express or implied to any intellectual property rights is granted by this document.

IQGeo encourages all users of its products to procure all necessary intellectual property licenses required to implement any concepts or applications and does not condone or encourage any intellectual property infringement and disclaims any responsibility related thereto. These intellectual property licenses may differ from country to country and it is the responsibility of those who develop the concepts or applications to be aware of and comply with different national license requirements.

Windows® is a registered trademark of Microsoft Corporation in the United States and/or other countries. The other names of actual companies and products mentioned herein are the trademarks of their respective owners.