# Printer Manager Readme

See Github to download and for details: https://github.com/ITAutomator/IntuneApp/tree/main/Printers

# Overview

Use Printer Manager to automatically set up a standard list of printers on your PCs. It works by ingesting printer drivers from a working PC and then packaging it for distribution. It handles both Intel and ARM drivers.

Printer Manager is Intune and script friendly and designed to work within the <u>IntuneApp</u> system.

```
------ Printer Manager Menu -------
[S] Setup all the CSV printers (to this PC) PC <-- CSV
[0] Setup one CSV printer (to this PC)
                                          PC <-- CSV
[V] Update a driver to the \Drivers folder PC --> CSV
[A] Add a local printer to CSV list
                                           PC --> CSV
[U] Uninstall the CSV listed printers
                                           PC (X) CSV
[R] Local printer deletion
                                           PC (X)
[D] Local driver deletion
[P] Local port deletion
                                           PC (X)
[E] Edit CSV Files manually
                                           CSV
[T] Detect if PC has CSV printers already
[I] Prep intune_settings.csv with these printers (for IntuneApp)
```

Printer Manager main menu

The program uses 3 key components, all added via the *Printer Manager* main menu.

#### PrinterManager PrintersToAdd.csv

A list of printers to add to PCs.

#### PrinterManager PrintersToRemove.csv

An (optional) list of obsolete printers to remove from PCs.

#### IntuneApp\Drivers

A folder of drivers used to install the added printers.

Both x64 and ARM65 drivers can be included.

# Setup Steps

Download the package and copy it to a central area.

Right-click and run PrinterManager (as Admin).cmd to start the main menu.

Note: The 2 main CSV files will be created if they don't exist.

Note: To facilitate different printer lists for different groups, use multiple copies of the package in different folders and update the lists independently:

```
Printers (Accounting Group)
Printers (Executive Group)
```

#### Main Menu

Printer Manager Menu	
[S] Setup all the CSV printers (to this PC)	PC < CSV
[O] Setup one CSV printer (to this PC)	PC < CSV
<pre>[V] Update a driver to the \Drivers folder</pre>	PC> CSV
[A] Add a local printer to CSV list	PC> CSV
[U] Uninstall the CSV listed printers	PC (X) CSV
[R] Local printer deletion	PC (X)
[D] Local driver deletion	PC (X)
[P] Local port deletion	PC (X)
[E] Edit CSV Files manually	CSV
[T] Detect if PC has CSV printers already	CSV
[I] Prep intune_settings.csv with these prin	ters (for IntuneApp)
[X] Exit	

#### Add a Printer

On a PC with the printer already installed use menu choice A.

[A] Add a local printer to CSV list

This will add the printer to the CSV and copy the drivers to the Drivers folder. The printer is now included in the package and will be distributed to other PCs Repeat adding as many printers as needed.

### Edit the CSV files

To fine tune your list use menu choice E

[E] Edit CSV Files manually

This will allow you to edit the list of printers.

Here you can also adjust the IP numbers if they change.

PrinterManager PrintersToAdd.csv

Column Name	<b>Example Contents</b>	Explanation
Printer	Contoso Room 101 Copier	Printer display name
Driver-x64	HP Universal\prnbrcl1.inf	<menu [a]="" handles="" option="" this=""></menu>
Driver-ARM64	HP Universal\armbrc1.inf	<menu [a]="" handles="" option="" this=""></menu>
Port	192.168.53.60	<menu [a]="" handles="" option="" this=""></menu>
Model		<pre><optional helpful="" info="" model=""></optional></pre>
URL		<pre><optional helpful="" url=""></optional></pre>

Settings		<menu [a]="" handles="" option="" this=""></menu>
Location	Room 101	<optional displayed<="" helpful="" info="" p=""></optional>
		by Windows>

#### Settings column

Settings are for keywords that control the default settings (color, duplexing, etc) for the installed printer.

If the settings value is empty, the driver defaults will be used.

During the *Add a Printer* process you will be asked to choose from a list of default combinations of settings.

This list can be adjusted.

#### PrinterManager Settings.csv

Description	Settings
Default	 <blank></blank>
LetterColor	Papersize=Letter,Collate=False,Color=True
LetterGreyscale	Papersize=Letter,Collate=False,Color=False
LetterColorDuplex	Papersize=Letter,Collate=False,Color=True,DuplexingMode=TwoSidedLongEdg
	e
LetterGreyscaleDuple	Papersize=Letter,Collate=False,Color=False,DuplexingMode=TwoSidedLongEd
X	ge
A4Color	Papersize=A4,Collate=False,Color=True

#### **Summary of Settings**

Settings are in the form: key=value,key=value,...

See here for a full list of these values: Link

Key	Value
Papersize	Letter or A4
DuplexingMode	TwoSidedLongEdge
Collate	True or False
Color	True or False

# Prep for Intune

If you are planning on distributing this package using the <a href="IntuneApp">IntuneApp</a> app package system, use menu choice I

[I] Prep intune\_settings.csv with these printers (for IntuneApp)

This will make the necessary changes to the *intune\_settings.csv* file so that Intune detection and installation will work properly in the IntuneApp system.

Essentially it puts the lists of printers in the app variables section of that csv file.

#### A note about ARM drivers

The package is CPU aware. If you add a printer from an ARM machine, the driver will be added to the ARM driver folder and its own ARM column in the CSV.

If you want the printer to work in both types of CPUs, use A to add the printer from both PC types to get both driver packages. But you will have two CSV rows. Use the values from both driver columns to merge the two CSV rows into a single row.

# Manual installation of the printers

Copy the package folder to a target PC.

 $Right\text{-}click\ and\ run\ Printer Manager\ (as\ Admin).cmd\ to\ get\ to\ the\ main\ menu.$ 

Use menu choice S or menu choice O to install the printers.

[S] Setup all the CSV printers (to this PC)

[0] Setup one CSV printer (to this PC)

Use menu choice N to Uninstall the printers.

[U] Uninstall the CSV listed printers

# Scripted installation of the printers

We recommend using the <u>IntuneApp</u> app package system as the easiest way of distributing the printer package.

Alternatively, use the -mode S command line to automate installations.

PrinterManager.ps1 -mode S

This will automatically make the menu choice S and install the printers.

PrinterManager.ps1 -mode U

This will automatically make the menu choice U and uninstall the printers.

PrinterManager.ps1 -mode T

This will automatically make the menu choice T to detect if the printers are installed.

#### More information

See also: <a href="https://www.itautomator.com/intuneapp">https://www.itautomator.com/intuneapp</a>
See also: <a href="https://github.com/ITAutomator/IntuneApp">https://github.com/ITAutomator/IntuneApp</a>